

Rocky Linux OS - Security Patch Update

04/2025



Notice

The information contained in this document is believed to be accurate in all respects but is not warranted by Mitel Networks™ Corporation (MITEL®).

The information is subject to change without notice and should not be construed in any way as a commitment by Mitel or any of its affiliates or subsidiaries.

Mitel and its affiliates and subsidiaries assume no responsibility for any errors or omissions in this document. Revisions of this document or new editions of it may be issued to incorporate such changes.

No part of this document can be reproduced or transmitted in any form or by any means - electronic or mechanical - for any purpose without written permission from Mitel Networks Corporation.

©Copyright 2025, Mitel Networks Corporation. All rights reserved.

Mitel® is a registered trademark of Mitel Networks Corporation.

Any reference to third party trademarks is for reference only and Mitel makes no representation of ownership of these trademarks.

CONTENTS

1	INTRODUCTION	2
2	UPDATE WITH ISO FILE	2
2.1	PREREQUISITES	2
2.2	SIMPLEX MIVOICE 5000 AND MIVOICE 5000 MANAGER	2
2.3	REDUNDANT MIVOICE 5000	2
2.3.1	RECOMMENDATIONS	2
2.3.2	DETAILED PROCEDURE	2
2.4	REDUNDANT MIVOICE 5000 MANAGER	3
2.4.1	RECOMMENDATIONS	3
2.4.2	DETAILED PROCEDURE	3
3	UPDATE IN REPOSITORY MODE	3
3.1	PREREQUISITES	3
3.2	SIMPLEX AND DUPLEX MIVOICE 5000 SYSTEM	3
4	CHECKING THE TRACES FILE	4

1 INTRODUCTION

This document describes the update process of a security patch for Rocky Linux, for MiVoice 5000 Server and MiVoice 5000 Manager environments in R8.0 minimum.

Redundant systems:

For a redundant system, the upgrade must be performed on the master and slave PCs (MiVoice 5000 Server or MiVoice 5000 Manager) with the recommendations made in Section 2.3 – Redundant MiVoice 5000 and 2.4 – Redundant MiVoice 5000 Manager.

2 UPDATE WITH ISO FILE

2.1 PREREQUISITES

- R8.0 MiVoice 5000 or MiVoice 5000 Manager PC
- At least 2 GB available on the "/" partition.

2.2 SIMPLEX MIVOICE 5000 AND MIVOICE 5000 MANAGER



WARNING: First back up the configuration.

- Log in as "**root**".
- Mount the ISO image provided: SECURITYPATCH_8.X_YZ_Private.iso.
 - Replace **YZ** with the edition of the patch.
- In a "**Terminal**" window, go to the mounting root.
- un the command "**./installClientPrivate.sh**".
- Reboot the PC.

2.3 REDUNDANT MIVOICE 5000

2.3.1 RECOMMENDATIONS

- For a **redundant MiVoice 5000** system, start the upgrade on the slave PC, to minimize service interruptions. Updates are possible on active and inactive PCs.
- On the **master** PC, check the duplication status (**drbdsetup status**).

2.3.2 DETAILED PROCEDURE

On the slave PC:

- Install the patches on the **slave** PC by referring to Section 2.2 – Simplex MiVoice 5000 and MiVoice 5000 Manager.
- Reboot the **slave** PC.
- Check that the duplication status (**drbdsetup status**) on the **master** PC is **primary/secondary**.

On the Master PC:

- Switch over to the **slave** PC, which becomes active.
- Check that the duplication status (**drbdsetup status**) on the **master** PC **secondary/primary**.
- Install the patches on the **master** PC by referring to Section 2.2 – Simplex MiVoice 5000 and MiVoice 5000 Manager.

- Reboot the **master** PC.
- Switch over to the **master** PC, which becomes active.
- Check the operation.

2.4 REDUNDANT MIVoice 5000 MANAGER

2.4.1 RECOMMENDATIONS

For a **redundant MiVoice 5000 Manager**, updates are possible only on the active PC.

2.4.2 DETAILED PROCEDURE

On the Master PC:

- Check that the duplication status (**drbdsetup status**) on the **master** PC is **primary/secondary**.
- Install the patches on the **master** PC by referring to Section **2.2 – Simplex MiVoice 5000 and MiVoice 5000**.
- Reboot the **master** PC. This leads the system to switch over to the **slave** PC.
- Check that the duplication status (**drbdsetup status**) on the **master** PC is **secondary/primary**.

On the slave PC:

- Install the patches on the **slave** PC by referring to Section **2.2 – Simplex MiVoice 5000 and MiVoice 5000 Manager**.
- Reboot the **slave** PC. This leads the system to switch over to the **master** PC.
- Check that the duplication status (**drbdsetup status**) on the **master** PC is **primary/secondary**.
- Check the operation.

3 UPDATE IN REPOSITORY MODE

3.1 PREREQUISITES

- Only available for **MiVoice 5000**
- PC running with R8.0.
- At least 2 GB available on the "/" partition.

3.2 SIMPLEX AND DUPLEX MIVoice 5000 SYSTEM

- There are several ways to update MiVoice 5000 patches in repository mode:
 - With the MITEL repository
 - With the repository server tool
 - With MiVoice 5000 Manager

For the last 2 cases, download the file **SECURITYPATCH_R8.X_YZ.zip** from the **Software Download Center** Server.

Refer to **MiVoice 5000 Server - Operating Manual** for more information.

4 CHECKING THE TRACES FILE

In case of technical issues after the update, it is possible to retrieve a trace file with the MiVoice 5000 Web Admin.

To retrieve the traces of the machine and download the traces file, go to menu **Telephony service>System>Expert>Processor access>Debug tools>Troubleshooting**.

