

MiCollab Advanced Messaging Live Reply for Lync Administration Guide

For version 6.1 and above

Notice

The information contained in this document is believed to be accurate in all respects but is not warranted by Mitel Networks™ Corporation (MITEL®). Mitel makes no warranty of any kind with regards to this material, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. The information is subject to change without notice and should not be construed in any way as a commitment by Mitel or any of its affiliates or subsidiaries. Mitel and its affiliates and subsidiaries assume no responsibility for any errors or omissions in this document. Revisions of this document or new editions of it may be issued to incorporate such changes.

No part of this document can be reproduced or transmitted in any form or by any means - electronic or mechanical - for any purpose without written permission from Mitel Networks Corporation.

Trademarks

The trademarks, service marks, logos and graphics (collectively "Trademarks") appearing on Mitel's Internet sites or in its publications are registered and unregistered trademarks of Mitel Networks Corporation (MNC) or its subsidiaries (collectively "Mitel") or others. Use of the Trademarks is prohibited without the express consent from Mitel. Please contact our legal department at legal@mitel.com for additional information. For a list of the worldwide Mitel Networks Corporation registered trademarks, please refer to the website: <http://www.mitel.com/trademarks>.

© Copyright 2016, Mitel Networks Corporation

All rights reserved

Contents

Preface	4
References	4
Documentation	4
Documentation Updates	5
Help	5
Document Conventions	5
Frequently Used Terms	6
Overview	8
What Is Live Reply?	8
MiCollab AM Installation Requirements	8
Subscriber Workstation System Requirements	8
Installing Live Reply	9
Installing Live Reply on a Workstation from the MiCollab AM Installation Media	9
Installing Live Reply on a Workstation from a Network File Share	10
Placing Live Reply on a Server	10
Installing Live Reply on a Workstation from a Server	10
Configuring Live Reply	10
Using Live Reply	12

Preface

This guide is written for Mitel certified MiCollab Advanced Messaging (MiCollab AM) technicians and administrators who are experienced with MiCollab AM and are familiar with its procedures and terminology. This book assumes you are familiar with MiCollab AM and the Microsoft Windows® operating system, and have a working knowledge of TCP/IP protocols, as well as a working knowledge of domain administration in a Windows Server environment.

This installation guide consists of the following parts:

- Installation requirements for your MiCollab AM server and client workstations
- Instructions for installing and configuring Live Reply

References

A catalog of technical documentation is included on the MiCollab AM Installation Media. If you are installing any advanced applications, such as Networking and Fax Server applications, you should refer to the appropriate technical documentation for application and installation information.

Documentation

The technical documentation is produced in the PDF format and requires the PDF reader to view it. The documentation set for this MiCollab AM includes the following documents and resources:

- **Developer Resources.** Contains programming guides and API references for developers for integrating the server clients and web applications with MiCollab AM.
- **Integration Technical Notes (ITN).** Contains a set of guides that describe the integration methods and instructions for a variety of phone systems to work with MiCollab AM. The ITNs are generally used by resellers or administrators who are experienced with MiCollab AM and familiar with the integration procedures and terminology.
- **Quick Reference Card (QRC).** Contains shortcuts and quick instructions telling subscribers how to access and use the messaging system.
- **Server Documentation.** Available as a PDF only. Contains administrative guides for administrators about installing, configuring, and administering the messaging system, and user guides for subscribers about accessing the messaging system and checking and sending messages.
- **Spare Parts Documentation.** Contains a set of guides that describe the instructions for installing and configuring hardware parts to work with MiCollab AM. These documents are written for Mitel certified MiCollab AM technicians who are experienced with MiCollab AM and familiar with the procedures and terminology.
- **Software Release Notice (SRN).** This notice introduces the new features, capabilities, and hardware/software requirements for the corresponding MiCollab AM version.

For more related documents, refer to the following list of references:

Table 1. References

Document Type	Document Title
Software Release Notice	Software Release Notice
Server Documentation	System Installation Guide
Server Documentation	System Administration Guide
Server Documentation	RightFax Administration Guide
Server Documentation	Unified Messaging for Microsoft Exchange 2007 Administration Guide
Server Documentation	Unified Messaging for Microsoft Exchange 2010 2013 2016 Administration Guide
Server Documentation	Unified Message for Microsoft Exchange 365 Administration Guide
Server Documentation	Unified Messaging for Lotus Notes and Domino Administration Guide
Server Documentation	Live Reply Administration Guide
Server Documentation	Web Phone Manager Administration Guide
Server Documentation	Unified Messaging Connection Manager online help

Documentation Updates

Documentation updates may be available from the following sources:

- Mitel certified technicians can view or download documents and program files from our partner web site: connect.mitel.com/connect

Help

The primary source of information about MiCollab AM is the online help available within any of its administrative utilities. You can access **Help** as follows:

- Click the **Help** button in the dialog box or window in which you are working
- Press the **F1** key at any time.

Document Conventions

The following conventions are used in this document:

- **Key Names.** Names of keys on the keyboard are shown in a box.

Example: **Enter**

When two keys must be pressed simultaneously, they are joined by a + sign.

Example: **Alt** + **Tab**

- **Reference to Document.** *Italics* fonts can also signify the titles of other documents.

Example: Refer to *System Installation Guide*.

- **UI Element Names.** Names of UI elements such as dialog windows, screens, menu items, tabs, buttons, icons, etc. are shown in bold.

Example: On the **Startup** screen, click the **Start** icon.

- **User Input.** Information required to be typed is shown in italics.

Example: Type the password *voicemail*.

- **Warning, Caution, Important, and Notes.** Text for the contents that require attention are shown as follows:

WARNING A warning paragraph advises you of circumstances that can result in the loss of data, harm to the system server platform, or personal harm.

CAUTION Failure to follow these recommendations can result in unauthorized access to the system and consequent loss of data.

IMPORTANT An important paragraph gives decision-making information or informs you of the order in which tasks need to be completed.

NOTE A note gives additional information, provides an explanation, or indicates an exception to the information in the preceding text.

Frequently Used Terms

Table 2. Frequently Used Terms

Terms	Description
System Server	<p>Term refers to an organization's computer platform(s) that have MiCollab AM software installed and handles the core system functions such as storing messages, database.</p> <p>It can also refer generically to the System Server platform, the Call Server platform, or both. The term is most often used to describe a software or</p>

	hardware installation or configuration practice where the role of the server platform is not specifically expressed.
Call Server	Term refers to an organization's computer platforms that have MiCollab AM software installed and serve as the interface to the system (PBX). The Call Server(s) interface with the System Server for the purpose of accessing messages, and database.

Overview

What Is Live Reply?

Live Reply for Microsoft Lync is an application that installs on a subscriber's workstation. It allows a subscriber to either right-click to call another Lync user or to place other calls from MiCollab AM via Lync. Live Reply request, MiCollab AM will ring the subscriber's extension and connect the call to the destination number.

MiCollab AM Installation Requirements

Subscriber workstations must meet or exceed the following requirements:

- MiCollab AM 6.1 or later

Subscriber Workstation System Requirements

Subscriber workstations must meet or exceed the following requirements:

- Windows Vista, 7, 8/8.1, or 10
- Either:
 - Microsoft Lync 2010
 - or 2013 with Update KB2760512 for Microsoft Lync 2013 with Update 15.0.4454.1509 (support.microsoft.com/kb/2812461).

Installing Live Reply

Live Reply can be installed either from a LAN file server or directly from the MiCollab AM Installation Media.

Installing Live Reply creates a MiCollab AM Desktop program group and installs an icon in the Windows Taskbar Notification Area.

Installing Live Reply software on a LAN file server requires an Administration Setup. Performing an Administration Setup copies the necessary software components of the MiCollab AM Installation Media to a shared directory on the LAN file server and creates a default subscriber profile. This client and profile can then be pushed to client workstations, or subscribers can pull from this shared location and run Setup to install Live Reply to their local hard disk drives.

IMPORTANT Do not perform an Administration Setup to the MiCollab AM server. Using the MiCollab AM server as a LAN file server can increase its vulnerability to viruses and negatively affect overall system performance.

Installing Live Reply on a Workstation from the MiCollab AM Installation Media

Before Live Reply can be configured, confirm that the following items are available for each subscriber workstation:

- A Subscriber mailbox on the MiCollab AM system
- A properly configured MiCollab AM extension.

To install Live Reply software on a LAN file server:

- 1 Insert the MiCollab AM Installation Media into the appropriate drive. The MiCollab AM installation process will start. If it doesn't, browse to the root folder of the installation media and open **start.hta**.
- 2 Locate the appropriate Live Reply application in the *End-User Clients* section.
- 3 Click the link and follow the installation instructions.

Installing Live Reply on a Workstation from a Network File Share

To facilitate deployment in larger organizations or in situations where physical access to the MiCollab AM Installation Media is not desirable or not practical, Live Reply may be placed on a centrally located file server and installed over the network.

Placing Live Reply on a Server

To install Live Reply software on a LAN file server:

- 1 Create a shared directory on the server from which users will be able to install the Live Reply application.
- 2 Insert the MiCollab AM Installation Media into the appropriate drive of the file server from which you want the client installed.
- 3 Browse to the Live Reply directory: *"drive:\Client Installs\Live Reply"*
- 4 Copy both the 32-bit and 64-bit directories to the server.
- 5 Notify subscribers of the file server and directory and of which version, 32-bit or 64-bit, they should install.

Installing Live Reply on a Workstation from a Server

Before Live Reply can be configured, confirm that the following items are available for each subscriber workstation:

- A Subscriber mailbox on the MiCollab AM system
- A properly configured MiCollab AM extension.

To install the Live Reply on a workstation from a network file server:

- 1 Locate the appropriate setup folder on the network file server. The location of this file was established during the implementation and then communicated to the subscriber base.
- 2 Double-click **Setup** to begin the setup process.
- 3 Follow the on-screen instructions to install the application. Configuring the application is done after it has installed.

Configuring Live Reply

Prior to a subscriber's first use of Live Reply, there are several unique settings that must be configured. Subscribers who are familiar with the necessary settings can perform this procedure themselves; for those subscribers who are not familiar with the settings, MIS support staff should perform the procedure.


To configure Live Reply:

- 1 In the Taskbar Notification Area, right-click the MiCollab AM icon and select Configure.



The configuration screen displays.

- 2 Enter the IP address of your MiCollab AM server in the Server box.



The image shows a 'Live Reply Configuration' dialog box with a title bar containing a phone icon and a close button. The dialog contains several input fields and buttons. On the left, labels are aligned with input fields: 'Server' (a wide text box), 'Mailbox' (a text box), 'Password' (a text box), 'Extension' (a text box), 'Transfer Type' (a dropdown menu showing 'Monitored'), and 'Logging' (a checkbox). On the right side of the dialog, there are four buttons: 'Test' (positioned next to the Mailbox field), 'Save' (positioned next to the Extension field), 'Cancel' (positioned below the Save button), and 'About' (positioned below the Cancel button).

- 3 Enter the subscriber mailbox number and password of the subscriber who will be using Live Reply in the **Mailbox** and **Password** fields.
- 4 Enter the extension number that will ring in the **Extension** field.
- 5 Enter the type of transfer that will connect the call in the **Transfer Type** field. Default is Monitored.
- 6 To create a log of activity for troubleshooting purposes, check the **Logging** box.
- 7 Click the **Test** button to verify that the server IP, mailbox number, and password work properly. If the test fails, verify those three entries.
- 8 Click **Save**.

Using Live Reply

To use live reply:

- 1 Right click on the contact name and select **Live Reply**. The contact card and Live Reply dialog will appear.
- 2 Select the phone number to call from the **Number** drop down. Some people may only have one number in their Exchange address book. You may also edit or manually enter a different number in the **Number** dropdown.
- 3 Click **Start Call**. MiCollab AM will ring your extension. The call will connect when you pick up your extension.

