

# POWERplay Web



## User manual

10/21/2020

### Product line neo, version 6.x

The described functions can be used with the following ASC products:

EVOIPneo

EVOLUTIONneo / XXL / eco

EVOflex (country-specific)

Please note that you can always find the most up-to-date technical documentation and product updates in the partner area on our website at <http://www.asctechnologies.com>.

Copyright © 2019 ASC Technologies AG. All rights reserved.

Windows is a registered trademark of Microsoft Corporation. VMware® is a registered trademark of VMware, Inc. All other marks and names mentioned herein may be trademarks of their respective companies.



## Contents

<b>1</b>	<b>General information .....</b>	<b>5</b>
<b>2</b>	<b>Introduction .....</b>	<b>6</b>
<b>3</b>	<b>System requirements.....</b>	<b>7</b>
<b>4</b>	<b>Licenses .....</b>	<b>8</b>
<b>5</b>	<b>Start application .....</b>	<b>9</b>
5.1	Single login.....	9
5.2	Combination login .....	10
5.3	Free seating login.....	11
5.4	Request new password.....	13
<b>6</b>	<b>User interface and general functions .....</b>	<b>15</b>
6.1	Navigation bar .....	17
6.2	Change language.....	17
6.3	Call up info .....	18
6.4	Change password .....	19
6.5	Change replay server .....	19
6.6	Player settings.....	20
6.7	Change navigation bar .....	20
6.8	Call up online help.....	20
<b>7</b>	<b>WEBcommand module .....</b>	<b>22</b>
7.1	Main view .....	22
7.1.1	Toolbar .....	23
7.1.2	Load selected conversation .....	23
7.2	Detail view.....	24
7.2.1	Enter additional data .....	25
<b>8</b>	<b>Conversation View module and Participant View module .....</b>	<b>26</b>
8.1	Main view .....	26
8.1.1	Toolbar of the main view .....	29
8.1.1.1	Load selected conversation .....	31
8.1.1.2	Export conversation .....	32
8.1.1.3	Add litigation hold.....	33
8.1.1.4	Remove litigation hold.....	34
8.1.1.5	Adjust table .....	35
8.1.1.6	Search.....	36
8.1.2	Change sort sequence .....	45
8.2	Detail view .....	45
8.2.1	Tab Details .....	46
8.2.2	Tab Participants .....	47
8.2.3	Tab Additional Data.....	48

8.2.3.1	Enter or change additional data .....	48
<b>9</b>	<b>Recording View module .....</b>	<b>49</b>
9.1	Main view .....	49
9.1.1	Toolbar .....	51
9.1.1.1	Load selected recording .....	52
9.1.1.2	Export recording .....	53
9.1.2	Change sort sequence .....	54
9.2	Detail view .....	55
9.2.1	Tab Details .....	56
9.2.2	Tab Participants .....	57
9.2.3	Tab Additional Data .....	57
9.2.3.1	Enter or change additional data .....	57
<b>10</b>	<b>Replay module .....</b>	<b>59</b>
10.1	Replay bar .....	59
10.1.1	Full view .....	60
10.1.2	Compressed view .....	60
10.1.3	Display of the loading states .....	61
10.1.4	Display of detected emotions .....	62
10.2	Functionality bar .....	62
10.2.1	Icons .....	63
10.2.2	Export all loaded elements .....	65
10.2.3	Create new bookmark .....	67
10.2.3.1	Create bookmarks with replay comment .....	67
10.2.3.2	Edit bookmarks with replay comment .....	69
10.2.3.3	Delete bookmarks with replay comment .....	69
10.2.4	Create new mute notification .....	70
10.2.4.1	Mute conversation section .....	70
10.2.4.2	Edit muted conversation section .....	71
10.2.4.3	Delete muted conversation section .....	71
10.2.5	Mark replay loop .....	72
10.3	Video Viewer .....	72
10.3.1	Option bar .....	74
10.3.2	Replay bar .....	74
10.4	Message Viewer .....	75
10.4.1	Main view .....	76
	<b>List of figures .....</b>	<b>78</b>
	<b>List of tables .....</b>	<b>81</b>
	<b>Glossary .....</b>	<b>82</b>

## General information

In the context of this document ASC represents ASC Technologies AG, its subsidiaries, branch offices, and distributors. An up-to-date overview of the aforementioned entities can be found at <https://www.asctechnologies.com>

ASC assumes no guarantee for the actuality, correctness, integrity or quality of the information provided in the manuals.

ASC regularly checks the content of the released manuals for consistency with the described hardware and software. Nevertheless, deviations cannot be excluded. Necessary revisions are included in subsequent editions.

Some aspects of the ASC technology are described in general terms to protect the ownership and the confidential information or trade secrets of ASC.

The software programs and the manuals of ASC are protected by copyright law. All rights on the manuals are reserved including the rights of reproduction and multiplication of any kind, be it photo mechanical, typographical or on digital data media. This also applies to translations. Copying the manuals, completely or in parts, is only allowed with written authorization of ASC.

Representative, if not defined otherwise, is the technical status at the time of the delivery of the software, the devices and the manuals of ASC. Technical changes without specified announcements are reserved. Previous manuals lose their validity.

The general conditions of sales and delivery of ASC in their latest version apply.

## 2 Introduction

---

### 2 Introduction

The application POWER~~play~~ Web is a browser-based software for searching and replaying conversations which have been saved in the recording system. Users can search and replay conversations on every computer with an installed browser and a network connection to the replay server.

To ensure the necessary safety during search and replay of the recordings, an encrypted connection ([SSL/TLS](#)) is used.

### 3 System requirements

---

#### 3 System requirements



For basic information about the necessary hardware and software components refer to the installation manual *Installation requirements*.

## 4 Licenses

License name	Number	Description
POWER <u>play</u> Web	1 per concurrent user	License for the usage of POW- ER <u>play</u> Web.

Tab. 1: Licenses of ASC

License name	Number	Description
WEB <u>command</u>	1 per concurrent user	License for the usage of WEB- <u>command</u> .
FIGER	1 per server	Licenses for project-specific Fiducia version of WEB <u>com- mand</u> . The license is required for free seating, too, among others.

Tab. 2: Optional licenses of ASC




## 5

## Start application

Start the browser and enter the [URL](#) of the application server in the address bar. Your system administrator will inform you about the [URL](#) for accessing the application.

After you have entered the URL, the following login screen is displayed.



The login screen features two tabs at the top: 'Login' (active) and 'Combination Login'. Below the tabs are two input fields labeled 'Login name\*' and 'Password\*'. A 'Forgot password?' link is positioned above a green 'Login' button.

Fig. 1: Login screen

In general, there are the following login options:


- Single login = normal user login, see [chapter "Single login", p. 9](#)
- Combination login, see [chapter "Combination login", p. 10](#).
- Free seating login, see [chapter "Free seating login", p. 11](#)



Your system administrator will tell you which login you have to use.

## 5.1

## Single login



This screen is identical to the general login screen, showing the 'Login' tab, input fields for 'Login name\*' and 'Password\*', a 'Forgot password?' link, and a green 'Login' button.

Fig. 2: Single login

1. Enter your user name and the password.
  2. Click on the button -> *Login*.
- ⇒ The welcome screen of the application appears.

If you have forgotten your password and requested a new one upon your last login, the following window appears:




Fig. 3: Your password has expired

3. In the entry field *Old password*, enter your new password you have received by e-mail.
4. In the entry field *New password*, enter your new, modified password.
5. In the entry field *Confirm password*, repeat your new, modified password.
6. Click on the button *OK*.  
⇒ The welcome screen of the application appears.

## 5.2

### Combination login

For safety reasons, it may be sensible to assign a combination user to a user. That way it can be ensured for instance that a supervisor only accesses recorded conversations when a member of the work council is present.

If a combination user has been defined, the actual user is only allowed to log in when the combination user has logged in, too. If entering the login data of a combination user is required, proceed as follows:

1. In the login window, click on the button *Combination Login*.





Fig. 4: Login

2. The window *Combination Login* appears.



The image shows a login interface with two tabs: 'Login' and 'Combination Login'. The 'Combination Login' tab is active. Below the tabs are four input fields: 'Login name\*', 'Password\*', 'Combination user\*', and 'Combination password\*'. Each field has a corresponding text input line. Below these fields is a link that says 'Forgot password?'. At the bottom is a green button labeled 'Login'.

Fig. 5: Combination login


3. Enter your user name and your password as well as the user name and password of your combination user.

4. Click on the button -> *Login*.

⇒ The welcome screen of the application appears.

To change to the normal login, if required, click on the button *Login*.

If you have forgotten your password and requested a new one upon your last login, the following window appears:



The image shows a dialog box with a blue header that says 'Your password has expired.' Below the header are three input fields: 'Old password\*', 'New password\*', and 'Confirm password\*'. Each field has a corresponding text input line. At the bottom right is a blue button labeled 'OK'.

Fig. 6: Your password has expired

5. In the entry field *Old password*, enter your new password you have received by e-mail.

6. In the entry field *New password*, enter your new, modified password.


7. In the entry field *Confirm password*, repeat your new, modified password.

8. Click on the button *OK*.

⇒ The welcome screen of the application appears.

### 5.3 Free seating login

Logging in to free seating is only possible with a WEBcommand license and a FIGER license.




The login form has two tabs: 'Login' (active) and 'Combination Login'. Under the 'Login' tab, there are two input fields: 'Login name\*' and 'Password\*'. Below these fields is a link 'Forgot password?'. At the bottom is a green button labeled 'Login'.

Fig. 7: Single login

1. Enter your user name and the password.
2. Click the button *Login*.

If you have forgotten your password and requested a new one upon your last login, the following window appears:




A blue header bar contains the text 'Your password has expired.'. Below this are three input fields: 'Old password\*', 'New password\*', and 'Confirm password\*'. At the bottom right is a blue button labeled 'OK'.

Fig. 8: Your password has expired

3. In the entry field *Old password*, enter your new password you have received by e-mail.
4. In the entry field *New password*, enter your new, modified password.
5. In the entry field *Confirm password*, repeat your new, modified password.
6. Click on the button *OK*.

If you have logged in the default way with user name and password, the following window appears:



The form is titled 'Device check'. It contains the instruction 'Start the authentication call and enter the PIN.' followed by two input fields: 'Phone number' and 'PIN'. To the right of the 'Phone number' field is a blue telephone icon. At the bottom are two buttons: a green 'Confirm PIN' button and a smaller 'Back' button.

Fig. 9: Free seating login


7. In the entry field *Phone number*, enter the current number of the extension. The entry format of the phone number depends on the [PBX](#).
8. Click on the icon 📞 (*Request new PIN*).
  - ⇒ You will be called on the indicated phone number and a 4-digit PIN will be announced.
9. In the entry field *PIN* enter the 4-digit you have been told.
10. Click the button *Confirm PIN*.
  - ⇒ The welcome screen of the application appears.

#### 5.4

#### Request new password

If you have forgotten your password, you can request a new one via the function *Forgot password?* in the different login windows.


1. Click on the text *Forgot password?*



The screenshot shows a login window with two tabs: 'Login' (active) and 'Combination Login'. Under the 'Login' tab, there are two input fields: 'Login name\*' and 'Password\*'. Below these fields is a link labeled 'Forgot password?'. At the bottom of the form is a green button labeled 'Login'.

Fig. 10: Login window

2. The window *Forgot password?* appears.



The screenshot shows a 'Forgot password?' window. It has a title 'Forgot password?' at the top. Below it is a single input field labeled 'Login name\*'. At the bottom of the form is a green button labeled 'Reset Password'. Below the button is a link labeled 'Back'.

Fig. 11: Request password

3. Enter your user name.
4. Click on the button -> *Reset Password*.
  - ⇒ You will receive an e-mail containing your new password.



---

For this function, your administrator has to have configured a corresponding e-mail server.  
Contact your system administrator if you do not receive an e-mail after this step.

---

5. To return to the login, click on the text *Back*.














Fig. 12: Welcome screen


1	Navigation bar	Contains the individual modules, see <a href="#">chapter "Navigation bar", p. 17</a> .
2	Main view	Displays all recorded conversations with the most important information in a list.
3	Detail view	Contains detailed information about the element selected in the main view.
4	 (Collapse)	Icon which allows collapsing or reducing the displayed areas.
	 (Expand)	Icon which allows expanding or opening the displayed areas.
5	 (Collapse)	Icon which allows collapsing the displayed areas.
6	Toolbar	Contains functions for the elements in the main view.
7		Shows the date when your password expires. To hide the icon, click on the button <i>Okay</i> .
8	 (Your latest login has failed. Please use the correct password.)	Shows that the latest attempt to log in to the application was not successful. Click on the warning icon to delete the error message. Always use the correct password to log in to the application.
9	 (Your last logoff was not correct. Please use the logoff button.)	Indicated that you have not logged off correctly when leaving the application the last time. Click on the warning icon to delete the error message. Always use the logoff icon to log off from the application.

10		<i>Change Password</i>	Menu item which allows changing your password, see <a href="#">chapter "Change password", p. 19.</a>
		<i>Change Replay Server</i>	Menu item which allows changing the replay server, see <a href="#">chapter "Change replay server", p. 19.</a>
		<i>Player Settings</i>	Menu item which allows changing the player settings, see <a href="#">chapter "Player settings", p. 20.</a>
		<i>Navigation Bar</i>	Menu item which allows changing the way the navigation bar is displayed, see <a href="#">chapter "Change navigation bar", p. 20.</a>
		<i>Language</i>	Menu item which allows selecting the language of the user interface, see <a href="#">chapter "Change language", p. 17.</a>
		<i>Resource String View</i>	Menu item which allows changing between the resource string view and the default view. This view is only available ASC-internally.
		<i>Info</i>	Menu item which allows calling up information about the version of the ASC software, see <a href="#">chapter "Call up info", p. 18.</a>
		<i>Logoff</i>	Menu item which allows logging off from the application.
11	User		Name of the logged-in user
12	Last login date		Shows the date of the last login.
13	Rows per page 50 		Shows the number of rows per page In the drop-down list, select how many rows per page are supposed to be displayed. You can choose 10, 20, 50 or 100 rows per page.
14	Range of the displayed sets of data		Shows the range of the displayed sets of data on the current page of the main view.
15			Buttons which allow browsing the pages of the main view.
16	<i>Last filtered on ...;</i> <i>Number of records: ...</i>		Shows the time of the last filtering (search) and the number of data sets. Up to 1000 data sets are determined according to the current list of search results and displayed in the main view. If available, further data sets are displayed when reaching the last page of the list of search results. The exact number can be determined by means of the function  ( <i>Count results</i> ). It counts all data sets meeting the criteria selected in the search.
17			Shows the Replay module for controlling the replay, see <a href="#">chapter "Replay module", p. 59.</a>



If the session has been inactive for a longer period of time, the application is closed automatically. Default value for the timeout: 30 minutes. The value can be adjusted by the administrator, see administration manual *System Configuration - User Management*.



To close the application, always use the logoff function.  
 (Logged in as) > Logoff.



## 6.1 Navigation bar

The individual modules of the application are displayed in the navigation bar.






Fig. 13: Navigation bar

You can hide the navigation bar by clicking in the icon  and expand it again by clicking on the icon .

### Short description of the modules

Module name	Description
<i>WEB\$command\$</i>	This module serves to control the recording (start or stop the recording). Additionally, users can view the current status of the deployed extension, replay the latest conversations, and add additional data.
<i>Conversation</i>	This module opens all recorded conversations in a list. The list of conversations combines the recording of the end device of the caller and the recording of the end device of the called person in one list entry.
<i>Participant View</i>	This module opens all recorded conversations in a list. The conversation list displays the recording of the end device of the caller and the recording of the end device of the called person as separate list entries.
<i>Recording View</i>	This module is only available with an Airbus PBX.  This module opens the recordings of all active participants in a table. A recording is a conversation segment that 1 participant actively participates in. Exclusively those conversation segments are considered that have taken place from the moment on a connection has been established between the participants (connect section). I. e. for two conversation participants two recordings (one for the calling party and one for the called party) are displayed in the table. These recordings have the same section ID but different active participants.

Tab. 3: Module descriptions



If a conversation is interrupted by consultations of other participants, it may be possible that additional list entries are displayed in the conversation list for these consultation conversation.



It depends on your function rights which of the described modules are available.

## 6.2 Change language



- Click on the menu item  *Logged in as* > *Language* in the top right corner of the user interface.  
⇒ The following window appears:






Fig. 14: Change language

2. Select the language from the drop-down list. Only languages that you have installed during the installation can be selected.
  - ⇒ The texts of the user interface are displayed in the selected language.


### 6.3 Call up info

1. Click on the menu item  *Logged in as > Info* in the top right corner of the user interface.
  - ⇒ The window *Installed Product Versions* appears. It contains information about the version of the *neo* software.

The following information is displayed:

Column Name	Description
<i>Server Name</i>	Name of the server. Click on the arrow  to display the history. In the history, the servers have been sorted by installation date beginning at the top with the first installation date.
<i>Connected</i>	The icon  indicates that the core is used in the current application.
<i>Product Version</i>	Information about the current product version
<i>EC Version</i>	Information about the current Enterprise Core version
<i>Last Start</i>	Date and time of the last system start
<i>Last Stop</i>	Date and time of the last system stop
<i>Installation Date</i>	Date and time of the installation Click on the arrow  in the column <i>Server Name</i> to display the information.

Tab. 4: Information





Installed Product Versions						
Server Name	Connected	Product Version	EC Version	Last Start	Last Stop	Installation Date
CTI-01		6.0.0-0.0	60.1.0	11/19/2018 10:32:09 AM	11/19/2018 10:34:55 AM	
REC-01		6.0.0-10.0	60.16.0	02/11/2019 7:31:46 AM	02/07/2019 10:42:18 AM	
REC-01		6.0.0-0.0	60.1.0			11/12/2018 10:47:18 AM
REC-01		6.0.0-1.0	60.2.0			11/19/2018 11:25:43 AM
REC-01		6.0.0-4.0	60.5.0			12/05/2018 11:17:53 AM
REC-01		6.0.0-8.0	60.10.0			01/09/2019 12:09:12 PM
REC-01		6.0.0-9.0	60.15.0			01/29/2019 12:30:27 PM
REC-01		6.0.0-10.0	60.16.0			02/07/2019 10:51:29 AM

Fig. 15: Installed Product Versions

2. To obtain additional information about the system, click on the button *Additional Information* in the bottom right corner of the window.
  - ⇒ The window *Additional Information* appears. It contains information about the license.



Additional Information

**License Information**

System ID:	2322891
Order ID:	66666666


Close


Fig. 16: Additional Information

## 6.4 Change password



If you use the function *Last Call Repeat*, the password must consists of numbers only.

- Click on the menu item  *Logged in as* > *Change Password* in the top right corner of the user interface.  
⇒ The following window appears:



Change Password


Old password\*

New password\*

Confirm password\*


OK Reset


Fig. 17: Change password

- Enter your old password.
- Enter your new password and confirm it.
- To save the change of the password, click on the button *OK*.  
To delete the entries without saving them, click on the button *Reset*.  
To cancel the change of the password, click on the icon  in the top right corner of the window.

Once you have successfully saved the changed password, you have to enter the new password upon opening the application the next time.


## 6.5 Change replay server

- Click on the menu item  *Logged in as* > *Change Replay Server* in the top right corner of the user interface.  
⇒ The following window appears:



Change Replay Server

Current replay server: Replay 1

Replay server:  


OK Cancel

Fig. 18: Change replay server

- Select the replay server from the drop-down list.
- To save the change, click on the button *OK*.  
To discard the change, click on the button *Cancel*.

### 6.6 Player settings

To be able to directly replay conversations by double-clicking on the conversation, carry out the following configuration:

1. Click on the menu item  (*Logged in as*) > *Player Settings* in the top right corner of the user interface.

⇒ The following window appears:





Fig. 19: Player settings

2. Activate the check box *Direct replay upon double click*.  
☒ = Direct replay upon double click has been activated.  
☐ = Direct replay upon double click has been deactivated.
3. To save the change, click on the button *OK*.  
 To discard the change, click on the button *Cancel*.

### 6.7 Change navigation bar

To collapse the navigation bar by default, carry out the following configuration:

1. Click on the menu item  (*Logged in as*) > *Navigation Bar* in the top right corner of the user interface.

⇒ The following window appears:





Fig. 20: Change navigation bar

2. Activate the check box *Collapsed*  
☒ = The collapsed navigation bar has been activated.  
☐ = The collapsed navigation bar has been deactivated.
3. To save the change, click on the button *OK*.  
 To discard the change, click on the button *Cancel*.

### 6.8 Call up online help

An online help is available at different locations in the application. You can call up the online help as follows:

Menu / Button	Menu item	Location	Result
<i>General</i>	<i>General Help</i>	Toolbar of the main view	By clicking on the menu item <i>General Help</i> , a description of the application you are currently viewing is opened.
	<i>Module Help</i>	Toolbar of the main view	By clicking on the menu item <i>Module Help</i> , a description of the module you are currently viewing is opened.

Menu / Button	Menu item	Location	Result
 <a href="#">Help</a>		Detail view / Additional window	A topic-specific help opens referring to the tab or the additional window you are currently viewing.

Tab. 5: Call up online help

There are the following options to navigate in the online help:

- Navigation bar on the left of the window
- Contents (via the menu item *Contents* in the header)
- Cross reference to additional information at the bottom of the page

## 7

## WEBcommand module

The WEBcommand module displays the current status of the deployed extension to control the recording (start/stop recording) of currently running conversations. In the WEBcommand module, you can replay the latest conversations and add additional data.

## 7.1

## Main view

The main view displays the current status of the deployed extension of the user.

When opening the module, the last 10 data sets are displayed automatically. At the top, the status of the deployed extension is displayed. In the remaining rows (a maximum of 10 rows are available), the latest conversations are displayed.



If conversation rules (view filters) apply for the logged-in user, then the main view only contains those entries which comply with these conversation rules.











WEBcommand ▾ General ▾						
	Start Time	Duration	Conversation Partner	Additional Data Complete	Extension	Recording ID
 					6300	
 					6301	
 					6302	
	08/28/2019 4:09:08 PM	00:00:45:452		✗	6301	42cc9d21-45de-4a82-be46-daef3666e37b
	08/28/2019 4:07:54 PM	00:00:24:141		✗	6301	c265450c-a664-4b4f-8c2a-f150b1815c09
	08/28/2019 4:07:20 PM	00:02:26:880		✗	6302	22f87440-9042-4864-a0c9-61a6432febb7
	08/28/2019 4:05:22 PM	00:00:27:411		✗	6301	d2ff0d5-94ef-46f0-974b-f316c0eb2d66
	08/28/2019 4:04:35 PM	00:02:19:906		✗	6300	5335c72e-ead5-4b2c-b055-c99a5fb3998e
	08/28/2019 2:15:47 PM	00:00:51:884		✗	6301	cd04bde0-36d5-4be2-9fb6-450ba90ae
	08/28/2019 2:15:18 PM	00:01:18:761		✗	6300	939162fe-3350-4c4d-ad7d-9cbd396c95e3






Fig. 21: Main view WEBcommand (example)



If a conversation is interrupted by consultations of other participants, it may be possible that additional list entries are displayed in the conversation list for these consultation conversation.

The main view displays the following information:

System data	
(1st row)	Displays the current status of the deployed extension to control the recording (start/stop recording) of currently running conversations.
 	<p> (Start recording)</p> <p>No conversation is currently active on the deployed extension. No recording can be started.</p> <p> (Start recording)</p> <p>A conversation is currently active on the deployed extension. The recording of the conversation can be started.</p>

	 (Recording is running) A conversation is currently active on the deployed extension. The conversation is being recorded.
	 (Stop recording) No conversation is currently active on the deployed extension. The recording of the conversation cannot be stopped.
	 (Stop recording) A conversation is currently active on the deployed extension. The conversation is being recorded and the recording can be stopped..
<i>Start Time</i>	Shows when the conversation was started.
<i>Duration</i>	Shows the duration of the conversation.
<i>Conversation Partner</i>	Shows the phone number of the conversation partner.
<i>Additional Data Complete</i>	Shows whether the mandatory fields for the additional data have been completed.  = Mandatory fields have been completed.  = Mandatory fields have not been completed. The mandatory fields in the detail view of the conversation are marked with a " * ". These fields must be completed.
<i>Extension</i>	Shows the number of the extension.
<i>Recording ID</i>	Shows the recording ID.

The toolbar of the main view contains further functions which can be used for the elements of the main view, see [chapter "Toolbar", p. 23](#).

### 7.1.1 Toolbar

The toolbar of the main view is located in the center window and offers different functions.



Fig. 22: Toolbar WEBcommand

In the following, you find a description of the icons.

<i>WEBcommand</i>	<i>Hide Conversations with Completed Additional Data</i>	Hides the conversations for which additional data have been completed from the table in the main view.
	<i>Display Conversations with Completed Additional Data</i>	Displays the latest conversations regardless of the condition of the additional data.
<i>General</i>	<i>General Help</i>	Via the menu item <i>General Help</i> , a description of the application you are currently viewing is opened. See <a href="#">chapter "Call up online help", p. 20</a> .

### 7.1.2 Load selected conversation

This function allows loading a conversation into the Replay module and replaying it there.


1. In the main view, double-click on the conversations you would like to replay.
- ⇒ The conversation is loaded into the Replay module and can be replayed there.  
For information about the functions of the Replay module see [chapter "Replay module", p. 59](#).

If a conversation is no longer displayed in the WEBcommand module, change to the Conversation module. There, you can view all conversations, select the respective conversation, load it into the Replay module and replay it there. See [chapter "Load selected conversation", p. 31](#).

## 7.2

### Detail view

The detail view displayed additional data and detailed information about the selected conversation in the main view.



< Details >

---

**Pflichtfelder**

---

Aufbewahrungsdauer \* 5 Jahre

Personalnummer \*

---

**Kundendaten**

---

Bearbeitungsnummer

Partnerrufnummer

Kommentar

---

**Consultant**

---

Phone number consultant 59631002

Employee ID Homer

---

**System data**

---

Start time 08/30/2019 8:48:43 AM

End time 08/30/2019 9:19:14 AM

Duration of recording 00:30:30

Conversation direction Inbound

RZBK

Recording ID 1de85fda-465a-4752-ab1f-fc06758a3cdf

Fig. 23: Detail view (example)

At the top of the detail view are the entry fields to enter additional data that the tenant has configured. These must be completed by the employee.

Additional data fields marked with a “ \* ” are mandatory fields. These fields must be completed.

At the bottom of the detail view there is the following information about the conversation:

Consultant	
<i>Phone number consultant</i>	Shows the phone number of the consultant.
<i>Employee ID</i>	Shows the employee ID of the consultant.
System data	
<i>Start time</i>	Shows the start time of the conversation.
<i>End time</i>	Shows the end time of the conversation.



<i>Duration of the recording</i>	Shows the duration of the conversation.
<i>Conversation direction</i>	Shows the conversation direction, whether this is an inbound or an outbound call. <ul style="list-style-type: none"> <li>• Inbound - Customer calls agent, externally incoming</li> <li>• Outbound - Agent calls customer, externally outgoing</li> <li>• Internal - Agent calls agent</li> </ul>
<i>RZBK</i>	Shows the number of the bank.
<i>Recording ID</i>	Shows the recording ID.

Once you have finished entering the additional data, click on the button **Save** to save changes.

### 7.2.1 Enter additional data

1. To add additional data for a conversation, select the conversation in the main view.
2. Enter the additional data in the detail view.  
Additional data fields marked with a “ \* ” are mandatory fields. These fields must be completed.
3. To save the entries, click on the button **Save**.

If a conversation is no longer displayed in the WEBcommand module, change to the Conversation module. There, you can see all conversations and enter additional data for a conversation, too. To do so, proceed as follows:

4. In the main view, click on the conversations for which you would like to enter additional data.
5. Enter the additional data in the detail view.  
Additional data fields marked with a “ \* ” are mandatory fields. These fields must be completed.
6. To save the entries, click on the button **Save**.

## 8

## Conversation View module and Participant View module

The Conversation module opens all recorded conversations in a list. The list of conversations combines the recording of the end device of the caller and the recording of the end device of the called person in one list entry.

The Participant View module opens all recorded conversations in a list. The conversation list displays the recording of the end device of the caller and the recording of the end device of the called person as separate list entries.

## 8.1

### Main view

The main view shows all recorded conversations in a list.



When opening the module, a search filter is set automatically so that only data sets of the last 14 days are displayed.

The function *Reset search* (🔍) does not deactivate this filter!

Click on the icon 🔍 (*Search*) to adjust the search filter to your requirements.



If conversation rules (view filters) apply for the logged-in user, then the main view only contains those entries which comply with these conversation rules.

<div> <span>🔄</span> <span>🔍</span> <span>Conversations ▾</span> <span>General ▾</span> </div>					
Loaded ▾	Conversation Type ▾	Start Time ▾	Data Start ▾	End Time ▾	Duration ▾
	📞	11/20/2018 11:33:57 AM	11/20/2018 11:33:57 AM	11/20/2018 11:34:27 AM	00:00:30:197
	📞	11/20/2018 11:33:36 AM	11/20/2018 11:33:39 AM	11/20/2018 11:34:01 AM	00:00:24:784
	📞	11/20/2018 11:33:33 AM	11/20/2018 11:33:55 AM	11/20/2018 11:34:28 AM	00:00:55:639
	📞	11/20/2018 11:33:19 AM	11/20/2018 11:33:26 AM	11/20/2018 11:34:27 AM	00:01:08:100
	📞	11/20/2018 11:32:56 AM	11/20/2018 11:32:59 AM	11/20/2018 11:33:21 AM	00:00:24:937
	📞	11/20/2018 11:32:39 AM	11/20/2018 11:32:47 AM	11/20/2018 11:33:07 AM	00:00:28:403
	📞	11/20/2018 11:31:33 AM	11/20/2018 11:31:55 AM	11/20/2018 11:33:23 AM	00:01:50:248
	📞	11/20/2018 11:31:17 AM	11/20/2018 11:31:17 AM	11/20/2018 11:31:47 AM	00:00:30:232
	📞	11/20/2018 11:30:56 AM	11/20/2018 11:30:59 AM	11/20/2018 11:31:20 AM	00:00:24:511

Rows per page 50 ▾ 1 - 50 of 298 🔍 << >> Last filtered on 11/26/2018 6:46:39 AM; Number of records: 298

Fig. 24: Main view



If a conversation is interrupted by consultations of other participants, it may be possible that additional list entries are displayed in the conversation list for these consultation conversation.

Depending on the configuration of the columns, the following information is displayed in the main view:

General	
<i>Participant View ID</i>	Shows the participant view ID.
<i>Loaded</i>	Shows whether the conversation has been loaded in the Replay module.



= Conversation has not been loaded.



= Conversation has been loaded.

The loaded conversation is assigned one of the colors from a predefined color palette. The order of the colors has been predetermined. If all colors from the color palette have been used in several loaded conversations, color assignment start over again. In the Replay module, the loaded conversation is displayed in the same color.

### Conversation Information

<i>Conversation ID</i>	Shows the conversation view ID.
<i>Start Time</i>	Shows when the conversation was started.
<i>Data Start</i>	Shows when the data part of the conversation starts.
<i>End Time</i>	Shows when the conversation was ended.
<i>Creation Date</i>	Shows when the conversation was created.
<i>Updated</i>	Shows when the conversation was updated for the last time.
<i>Duration</i>	Shows the duration of the conversation.
<i>Conversation Direction</i>	<p>The conversation direction shows whether this is an inbound or an outbound call.</p> <ul style="list-style-type: none"> <li>• Inbound - Customer calls agent, externally incoming</li> <li>• Outbound - Agent calls customer, externally outgoing</li> <li>• Internal - Agent calls agent</li> </ul>
<i>Call Direction</i>	<p>Shows the call direction:</p> <ul style="list-style-type: none"> <li>• Incoming</li> <li>• Outgoing</li> <li>• Transferred</li> </ul>
<i>Archived</i>	<p>Shows whether the conversation has been archived.</p> <p>✓ = archived</p> <p>✗ = not archived</p>
<i>Comment</i>	Shows the comment.
<i>Conversation Type</i>	<p>Displays the type of the conversation.</p> <p>Call = call/video call</p> <p>Work item = work item (screen)</p> <p>Call and screen recording = call and screen</p> <p>Text = SMS/SDS</p> <p>Chat = chat</p>
<i>Deletion Time</i>	<p>Shows when the conversation is deleted automatically.</p> <p><i>Litigation Hold</i> = Conversation can neither be deleted automatically nor manually.</p>

### Statistics of the Conversation

<i>Number of Ringing Sections</i>	Shows the number of ringing sections.
<i>Duration of Ringing Sections</i>	Shows the duration of the ringing sections.

<i>Number of Hold Sections</i>	Shows the number of hold sections.
<i>Duration of Hold Sections</i>	Shows the duration of the hold sections.
<i>Number of Connected Sections</i>	Shows the number of connected sections.
<i>Duration of Connected Sections</i>	Shows the duration of the connected sections.
<i>Number of Failed Callbacks</i>	Shows the number of failed callbacks.
<i>Number of Successful Callbacks</i>	Shows the number of successful callbacks.
<i>Conversation ID of Callback Request</i>	Shows the conversation ID of the callback request.

#### Calling Party Information

<i>Calling Party Name</i>	Shows the name of the calling party (last name, first name).
<i>Calling Party PBX Agent ID</i>	Shows the PBX Agent ID of the calling party.
<i>Calling Party Phone Number</i>	Shows the phone number of the calling party.
<i>Calling Party Employee Number</i>	Shows the employee number of the calling party.
<i>Calling Party Device Name</i>	Shows the device name of the turret or of the phone of the calling party.

#### Called Party Information

<i>Called Party Name</i>	Shows the name of the called party (last name, first name).
<i>Called Party PBX Agent ID</i>	Shows the PBX Agent ID of the called party.
<i>Called Party Phone Number</i>	Shows the phone number of the called party.
<i>Called Party Employee Number</i>	Shows the employee number of the called party.
<i>Called Party Device Name</i>	Shows the device name of the turret or of the phone of the called party.

#### 1st-Connected Participant Information

<i>1st-Connected Name</i>	Shows the name of the 1st connected (last name, first name).
<i>1st-Connected PBX Agent ID</i>	Shows the PBX Agent ID of the 1st connected.
<i>1st-Connected Phone Number</i>	Shows the phone number of the 1st connected.
<i>1st-Connected Employee Number</i>	Shows the employee number of the 1st connected.
<i>1st-Connected Device Name</i>	Shows the device name of the turret or of the phone of the first connected.

#### Participant Information

<i>Participant Name</i>	Shows the name of the participant (last name, first name).
-------------------------	--

<i>PBX Agent ID</i>	Shows the PBX Agent ID.
<i>Participant Phone Number</i>	Shows the phone number of the participant.
<i>Participant Employee Number</i>	Shows the employee number of the participant.
<i>Device Name</i>	Shows the device name of the turret or of the phone of the participant.

#### Additional Data

<i>Display Name Additional Data</i>	<p>Shows the additional conversation data.</p> <p>You have to have the respective rights to be able to display the additional data.</p> <p>For information about the configuration of the additional data refer to the administration manual <i>System Configuration - Additional Data module</i>.</p>
-------------------------------------	--

Information about the configuration of the table can be found in [chapter "Adjust table", p. 35](#).





The toolbar of the main view contains all functions which can be used for the elements of the main view, see [chapter "Toolbar of the main view", p. 29](#).

The sort sequence of the conversations can be adjusted arbitrarily, see [chapter "Change sort sequence", p. 45](#).

At the bottom edge of the main view, buttons allow you to browse the pages of the main view and indicate which page you are on.

51 - 100 of 298    ◀ ◁ ▷ ▶

Fig. 25: Changing pages

	Jumps to the first page of the main view.
	Jumps to the previous page of the main view.
51 - 100 of 298	Shows the range of the displayed sets of data on the current page of the main view.
	Jumps to the next page of the main view.
	Jumps to the last page of the main view.

On the pages of the main view, you can navigate by using the scrollbars.

### 8.1.1





#### Toolbar of the main view






The toolbar of the main view is located in the center window and contains different functions.



Fig. 26: Toolbar of the main view

In the following, you find a description of the icons.

	<i>Refresh</i>	Refreshes the conversation table in the main view.
	<i>Search</i>	Opens the window of the search function. The search function allows searching systematically for sets of data which meet certain criteria, see <a href="#">chapter "Search", p. 36</a> .
		When opening the module, a search filter is set automatically so that only data sets of the last 14 days are displayed. The function by means of the icon  ( <i>Reset search</i> ) does not deactivate this filter!


		The icon  (Search) is displayed whenever the search has been adjusted by means of a filter.
	<i>Reset Search</i>	Resets all manually entered search criteria. The search is started without manual filter settings.
	<i>Count Results</i>	Determines the number of data sets according to the current list of search results in the main view.  The number of data sets is displayed at the bottom of the main view, see pos. 11 in <a href="#">Fig. 12, p. 15</a> .
	<i>Load selected conversation</i>	Loads a selected conversation into the Replay module for replay, see <a href="#">chapter "Load selected conversation", p. 31</a> .
	<i>Delete</i>	Deletes a selected conversation.  If a recording is deleted from the Conversation module, all corresponding recordings from the Participant View module as well as the corresponding session are deleted.
<i>Conversations</i>	<i>Export</i>	Saves the audio data of the selected conversation as <a href="#">WAVE</a> file and the corresponding additional conversation data as CSV file on the hard disk of your computer, see <a href="#">chapter "Export conversation", p. 32</a> .
	<i>Repeat Last Conversation</i>	Loads the conversation most recently saved in the database into the Replay module.
	<i>Add Litigation Hold</i>	Sets the selected conversations to litigation hold mode so that they can neither be deleted automatically nor manually. See <a href="#">chapter "Add litigation hold", p. 33</a>  This function serves to retain conversations as evidence in case of legal disputes. As a conversation may be piece of evidence in more than one law suit, it is possible to add several litigation holds with different litigation hold IDs.  <b>NOTICE!</b> This feature is not suitable when using large amounts of data. In this case, performance issues could arise.
	<i>Remove Litigation Hold</i>	Removes selected conversations from the litigation hold mode. See <a href="#">chapter "Remove litigation hold", p. 34</a>  Several litigation holds with different litigation hold IDs can be applied to the conversations. Once all litigation holds have been removed from the conversations, the conversations may be deleted automatically or manually.
<i>General</i>	<i>Adjust Table</i>	Opens the window <i>Table Configuration</i> , see <a href="#">chapter "Adjust table", p. 35</a> .
	<i>General Help</i>	Via the menu item <i>General Help</i> , a description of the application you are currently viewing is opened. See <a href="#">chapter "Call up online help", p. 20</a> .
	<i>Module Help</i>	Via the menu item <i>Module Help</i> , a description of the module you are currently viewing is opened. See <a href="#">chapter "Call up online help", p. 20</a> .



It depends on your function rights which of the described functions are available.

## 8.1.1.1 Load selected conversation

This function allows loading conversations into the Replay module and replaying them there.

- In the main view, select the element you would like to replay.  
To select several elements or to revoke the selection, click on the respective line while holding the [Ctrl] key down.  
**NOTICE!** If you would like to select several elements, the earliest start time and the latest end time must not be more than 24 hours apart.
- Click on the icon  (*Load selected conversation*).






Loaded	Conversation Type	Start Time	Data Start	End Time	
		11/20/2018 11:33:57 AM	11/20/2018 11:33:57 AM	11/20/2018 11:3	197
		11/20/2018 11:33:36 AM	11/20/2018 11:33:39 AM	11/20/2018 11:3	784
		11/20/2018 11:33:33 AM	11/20/2018 11:33:55 AM	11/20/2018 11:3	639
		11/20/2018 11:33:19 AM	11/20/2018 11:33:26 AM	11/20/2018 11:3	100
		11/20/2018 11:32:56 AM	11/20/2018 11:32:59 AM	11/20/2018 11:33:21 AM	00:00:24:937

Fig. 27: Load selected conversations

- Select one of the following options:

<i>Load All</i>	<p>The entire recorded conversation is loaded into the Replay module.</p> <p>If a screen recording or a camera recording has been saved, then the screen video or the camera video is displayed in the Video Viewer of the Replay module.</p> <p>If a chat text or a text message (SMS or SDS) has been saved, then the chat text or the text message is displayed in the Message Viewer of the Replay module.</p>
<i>Load Voice Recording</i>	<p>The voice recording of the conversation is loaded into the Replay module.</p> <p>This option is only active if a voice recording has been saved for the selected conversation.</p>
<i>Load Screen Recording</i>	<p>The screen recording of the conversation is loaded into Video Viewer of the Replay module.</p> <p>This option is only active if a screen recording has been saved for the selected conversation.</p>
<i>Load Text Message</i>	<p>The text message (SMS or SDS) of the conversation is loaded into the Message Viewer of the Replay module.</p> <p>This option is only active if a text message has been saved for the selected conversation.</p>
<i>Load Chat Text</i>	<p>The chat text of the conversation is loaded into the Message Viewer of the Replay module.</p> <p>This option is only active if a chat text has been saved for the selected conversation.</p>
<i>Load Video</i>	<p>The camera recording of the conversation is loaded into the Video Viewer of the Replay module.</p> <p>This option is only active if a camera recording has been saved for the selected conversation.</p>



- The conversations are loaded into the Replay module and can be replayed there.  
For information about the functions of the Replay module see [chapter "Replay module", p. 59](#).



A conversation can be loaded into the Replay module and replayed there by double-clicking on the element in the main view.

## 8.1.1.2 Export conversation

- In the main view, select the conversations you would like to export.  
To select several conversations or to cancel a selection, hold the [Ctrl] key down and click on the respective line.





Loaded	Conversation Type	Start Time	Data Start	End Time	Duration	Delete Time
		12/16/2018 11:48:00 PM		12/16/2018 11:48:16 PM	00:00:16:469	12/30/9999 1:00:00 PM
		12/16/2018 11:47:59 PM	12/16/2018 11:48:13 PM	12/16/2018 11:48:16 PM	00:00:16:922	12/30/9999 1:00:00 PM
		12/16/2018 11:47:51 PM	12/16/2018 11:47:53 PM	12/16/2018 11:48:16 PM	00:00:25:268	12/30/9999 1:00:00 PM

Fig. 28: Select conversations

- Click on the menu item *Conversations > Export* in the toolbar of the main view.  
⇒ The following window appears:



**Save As**

Select whether you would like to export one file or several files

☒ **One**  
☐ **Several**  
☐ **Fragment**

Select the media to be exported

☐ **Audio** PCM Wave  
☐ **Video**  
☐ **Screen**  
☐ **Chat**  
☐ **SMS**

You can enter an optional password to protect the ZIP file

**Password**   
**Password**

OK Cancel

Fig. 29: Save as

- Select the respective option in the window *Save As*.

<i>Single</i>	Mixes all recordings of one or several conversations in one file.
<i>Several</i>	Creates its own file for each recording to be saved.
<i>Fragment</i>	Only data contained in the set loop are saved. All other data is discarded.
<i>Audio</i>	Saves the audio data. Select the audio format from the drop-down list: <ul style="list-style-type: none"> <li>• <i>PCM Wave</i></li> </ul>



	<p>With <b>PCM</b>, the output file is not compressed and can be replayed by almost any player. This method requires a lot of storage capacity.</p> <ul style="list-style-type: none"> <li>• <b>MP3</b></li> </ul> <p>With <b>MP3</b>, the output file is compressed and can be replayed by almost any player. This method requires less storage capacity.</p>
<b>Video</b>	Saves the <b>video data</b> .
<b>Screen</b>	Saves the screen recordings.
<b>Chat</b>	Saves the chat text.
<b>SMS</b>	Saves the SMS data.
<b>Password</b>	Protects the ZIP file with a password.

- Click on the button **OK**.  
⇒ The following window appears:




Fig. 30: Save conversations

- Select the option **Save File**.
- Click on the button **OK**.  
⇒ The elements are exported to the local download directory in a ZIP file.  
The ZIP file contains the following files:  
The audio data is saved as **WAVE** file(s).  
Audio data and screen recordings are saved as MP4 file(s).  
Video data is saved as MP4 file(s).  
Screen data is saved as MP4 file(s).  
The corresponding meta data is saved in the same directory as CSV file(s) under the same file name.  
Chat texts are saved as **XML** file(s).  
SMS data is saved as **XML** file(s).

### 8.1.1.3 Add litigation hold

- In the main view, select the conversations you would like to set to litigation hold mode.  
To select several conversations or to cancel a selection, hold the [Ctrl] key down and click on the respective line.

Loaded	Conversation Type	Start Time	Data Start	End Time	Duration	Delete Time
		12/16/2018 11:48:00 PM		12/16/2018 11:48:16 PM	00:00:16:469	12/30/9999 1:00:00 PM
		12/16/2018 11:47:59 PM	12/16/2018 11:48:13 PM	12/16/2018 11:48:16 PM	00:00:16:922	12/30/9999 1:00:00 PM
		12/16/2018 11:47:51 PM	12/16/2018 11:47:53 PM	12/16/2018 11:48:16 PM	00:00:25:268	12/30/9999 1:00:00 PM

Fig. 31: Select conversations

- Click on the menu item *Conversations > Add Litigation Hold* in the toolbar of the main view.  
⇒ The following window appears:

Add Litigation Hold

Litigation Hold ID

OK Cancel

Fig. 32: Add litigation hold

- Enter a name for the litigation hold mode in the entry field *Litigation Hold ID*. This name that is used to lock the conversation is necessary to remove the litigation hold.
- Click on the button *OK*.  
⇒ The selected conversations are set to litigation hold mode and can neither be deleted automatically nor manually.  
The status *Litigation Hold* is displayed in the main view in the column *Deletion Time*.

Loaded	Conversation Type	Start Time	Data Start	End Time	Duration	Delete Time
		16.12.2018 23:48:00		16.12.2018 23:48:16	00:00:16:469	30.12.9999 13:00:00
		16.12.2018 23:47:59	16.12.2018 23:48:13	16.12.2018 23:48:16	00:00:16:922	Litigation Hold
		16.12.2018 23:47:51	16.12.2018 23:47:53	16.12.2018 23:48:16	00:00:25:268	30.12.9999 13:00:00

Fig. 33: Display of a conversation in litigation hold mode



Several litigation holds with different litigation hold IDs can be applied to the conversations.

#### 8.1.1.4

#### Remove litigation hold


- In the main view, select the conversations you would like to remove from the litigation hold. To select several conversations or to cancel a selection, hold the [Ctrl] key down and click on the respective line.

Loaded	Conversation Type	Start Time	Data Start	End Time	Duration	Delete Time
		16.12.2018 23:48:00		16.12.2018 23:48:16	00:00:16:469	30.12.9999 13:00:00
		16.12.2018 23:47:59	16.12.2018 23:48:13	16.12.2018 23:48:16	00:00:16:922	Litigation Hold
		16.12.2018 23:47:51	16.12.2018 23:47:53	16.12.2018 23:48:16	00:00:25:268	30.12.9999 13:00:00

Fig. 34: Select conversations

- Click on the menu item *Conversations > Remove Litigation Hold* in the toolbar of the main view.

⇒ The following window appears:



Remove Litigation Hold

Litigation Hold ID

OK Cancel

Fig. 35: Remove litigation hold

3. Enter the name for the litigation hold mode in the entry field *Litigation Hold ID*.
4. Click on the button **OK**.

⇒ The selected conversations are removed from litigation hold mode.



Several litigation holds with different litigation hold IDs can be applied to the conversations. Once all litigation holds have been removed from the conversations, the conversations may be deleted automatically or manually.

#### 8.1.1.5

#### Adjust table

This function allows adjusting the order of the columns in the table of the main view.

1. Click on the menu item *General > Adjust Table* in the toolbar of the main view.

⇒ The window *Table Configuration* appears.




Table Configuration

Rows per page 50

Available	Assigned
Creation Date	Loaded
Updated	Conversation Type
Conversation ID	Start Time
Customer ID	Data Start
Transaction ID	End Time
Litigation	Duration
	Deletion Time
	Conversation Direction
	Calling Party PBX Agent ID

☐ Save as default configuration


Default Apply Cancel

Fig. 36: Adjust table of the main view (example)


The different columns can be moved within a list or from one list to the other by dragging them to and dropping them in the required position. Double-clicking on one column moves the column to the end of the opposite list.

The following functions are available:

Rows per page 50	Number of rows per page.
<b>Save as default configuration</b>	If this check box is activated, the table configuration is saved as default for the employees of the tenant upon applying the changes. <b>NOTICE!</b> The option is only displayed if you have the respective right for this function.

Default	Resets the configuration in the window <i>Table Configuration</i> to the default settings and closes the window.
Apply	<p>Saves all changes and closes the window <i>Table Configuration</i>.</p> <p>If the check box <i>Save as default configuration</i> has been activated, a dialog window appears upon applying the changes. In the dialog window click on the button <i>Yes</i> or <i>No</i>.</p> <p><b>Yes</b></p> <p>The current table configuration is saved as default for the tenant. All table configurations existing for this module are deleted from the database.</p> <p>When opening the module, the employees of the tenant see the new table configuration that has been saved.</p> <p><b>No</b></p> <p>The current table configuration is saved as default for the tenant. When opening the module, the employees of the tenant see the new table configuration that has been saved if no other individual configuration has been saved.</p>
	Closes the window <i>Table Configuration</i> without applying the changes.

In the list *Available*, all columns which are currently not used are displayed. In the list *Assigned*, all columns used in the main view are displayed. The entries arranged from top to bottom correspond to the columns arranged from left to right in the main view.



2. Configure the column view according to your requirements.
3. In the drop-down list, select how many rows per page are supposed to be displayed.  
⇒ You can choose 10, 20, 50 or 100 rows per page.
4. To apply the changes in the current view, click on the button *Apply*.  
To discard the changes and close the window, click on the icon .

#### 8.1.1.5.1 Change column width of the table


To change the column width of the table in the main view individually, proceed as follows:

1. Left-click on the column of the header, hold the mouse key down, and drag the column to the respective width.

#### 8.1.1.6 Search

The function *Search* ( or ) allows searching for selected criteria systematically. Every search query can be saved to be used again.



The icon  is displayed whenever the search has been adjusted by means of a filter.



If conversation rules (view filters) apply for the logged-in user, then predefined search settings are displayed in the search criteria which comply with these conversation rules. You cannot delete these user-specific filter settings or search settings: however, you can add new ones and thus additionally filter the displayed entries in the main view.

Search Criteria
✕

Name of the search

- ▶ Conversation Information
- ▶ Statistics of the Conversation
- ▶ Calling Party Information
- ▶ Called Party Information
- ▶ 1st-Connected Participant Information
- ▼ General

Creation date	inactive	▼	★
Updated	inactive	▼	★

▶ Additional Data

^
Search   Reset   Back ▼

Fig. 37: Search criteria (example)

The following functions are available:

▶	Shows the content of the search category.
▼	Hides the content of the search category.
★	Adds the search criterion to the list of favorites.
★	Removes the search criterion from the list of favorites.
^	Hides the content of the window.
▼	Shows the content of the window.
Search	Starts the search.
Reset	Resets all manually entered search criteria.
<span style="border: 1px solid #ccc; padding: 2px 5px;">Back</span> ▼	Button <i>Back</i> shows the window with the saved search settings. Icon ▼ allows saving search criteria and deleting saved search settings.
✕	Closes the window <i>Search Criterion</i> .

#### 8.1.1.6.1 Search criteria




For the search, different search criteria are available which are divided in several search categories. It depends on the respective module which search criteria are available.

For all search criteria, you can select different comparison parameters from a drop-down list. In general, the following comparison parameters are available:



<i>inactive</i>	The search criterion is ignored for the search.
<i>between</i>	A search is made for all objects within the entered range. The initial and the final values are included in the search result.
<i>Period (indiv.)</i>	A search is made for all objects in the selected period of time.  In the entry field, enter the period in the following format: <i>month-days-hours-minutes</i> . As an example, the entry <i>03-05-15-20</i> means that a search is made for conversations from the last 3 months, 5 days, 15 hours, and 20 minutes.
<i>Period</i>	A search is made for all objects in the selected period of time.
<i>equal</i>	A search is made for all objects which exactly match the entered value.

<i>not equal</i>	A search is made for all objects which do not match the entered value.
<i>greater or equal</i>	A search is made for all objects the value of which is greater than or equal to the entered value.
<i>greater than</i>	A search is made for all objects the value of which is greater than the entered value.
<i>smaller or equal</i>	A search is made for all objects the value of which is smaller than or equal to the entered value.
<i>smaller than</i>	A search is made for all objects the value of which is smaller than the entered value.
<i>starts with</i>	A search is made for all objects which start with the entered value.
<i>doesn't start with</i>	A search is made for all objects which do not start with the entered value.
<i>ends with</i>	A search is made for all objects which end with the entered value.
<i>doesn't end with</i>	A search is made for all objects which do not end with the entered value.
<i>contains</i>	A search is made for all objects which contain the entered value.
<i>doesn't contain</i>	A search is made for all objects which do not contain the entered value.
<i>in</i>	One or several values are entered which are supposed to be searched for. The search displays all entries which match one of these values.
<i>not in</i>	One or several values are entered which are supposed to be searched for. The search displays all entries which do not match one of these values.

Depending on the search criterion, there are different options to enter or select comparison values:

- If only one entry field is displayed, enter the value directly into the entry field via the keyboard.
- If a drop-down list is displayed, select the value from the drop-down list.
- If a rotating field is displayed, click on one of the arrows to increase or decrease the value.
- If several values can be entered, enter the value directly in the entry field via the keyboard and click on the icon  on the right of the entry field.  
To remove a value from the list, click on the icon  on the right of the value.
- If different values are displayed in combination with a check box, select a value by marking the respective check box.
- If entering a date is required, enter the date directly via the keyboard or via the icon .

#### 8.1.1.6.2 Run a search

1. In the toolbar, click on the icon  or  (Search).
  - ⇒ If no saved search settings exist, the window with the search criteria appears, see [Fig. 39, p. 39](#).
  - ⇒ If saved search settings exist, the window with the saved search settings appears.




Fig. 38: Saved search settings (example)

2. If you would like to use one of the saved search settings, click on the line with the name of the saved search settings.
  - ⇒ The window of the search criteria appears.
  - ⇒ The saved search settings are loaded in the window with the search criteria.
3. If you do not want to use a saved search setting but define new search settings instead, click on the button *New Search*.
  - ⇒ The window of the search criteria appears.





Fig. 39: Search Criteria (example)

4. Set the respective search criteria, see [chapter "Search criteria", p. 37](#).
5. Click on the button *Search*.
  - ⇒ In the main view, the results are displayed.
6. To save the entered search criteria see [chapter "Save search settings", p. 39](#).  
 To reset all manually entered search criteria, click on the button *Reset*.  
 To close the window *Search Criteria*, click on the icon .

#### 8.1.1.6.3 Save search settings

You can save previously defined search settings.

1. Set the respective search criteria, see [chapter "Search criteria", p. 37](#).
2. Enter a name for the search settings in the entry field *Name of the search*.
3. If no saved search settings exist, click on the button *Save*.
  - ⇒ The entered search settings are saved.




Fig. 40: Save search settings (example)

4. If saved search settings exist, click on the icon ▼ on the right of the button *Back* and select the menu item *Save* in the drop-down list.  
⇒ The entered search settings are saved.







Fig. 41: Save search settings (example)

#### 8.1.1.6.4 Edit saved search settings

1. In the toolbar, click on the icon  or  (*Search*).
2. If the window with the search criteria appears, see Fig. 39, p. 39, click on the button *Back*.
3. The window with the saved search settings appears.





Search Criteria

Chat

All


< >

^

New Search ...

Fig. 42: Saved search settings (example)

4. Click on the line with the name of the saved search settings that you would like to edit.
  - ⇒ The window with the search criteria appears.
  - ⇒ The saved search settings are loaded in the window with the search criteria.



Search Criteria

Name of the search Chat

▶ Conversation Information

▶ Statistics of the Conversation

▶ Calling Party Information

▶ Called Party Information

▶ 1st-Connected Participant Information

▼ General

Creation date between 11/01/2018 12:00 and 11/28/2018 2:18:12

Updated inactive

▶ Additional Data



^ Search Reset Back


Fig. 43: Saved search settings loaded (example)

5. Adjust the search criteria according to your requirements.
6. To save the changed search settings under the same name, proceed as follows:
  - Click on the icon ▼ on the right of the button *Back*.
  - Select the menu item *Save* in the drop-down list.
 To save the changed search settings under a different name, proceed as follows:
  - Enter a new name for the search in the entry field *Name of the search*.
  - Click on the icon ▼ on the right of the button *Back*.
  - Select the menu item *Save* in the drop-down list.

#### 8.1.1.6.5 Search via saved search settings

If you have saved search settings (see [chapter "Save search settings", p. 39](#)), you can quickly search for the saved search criteria.

1. In the toolbar, click on the icon  or  (*Search*).
2. If the window with the search criteria appears, see [Fig. 39, p. 39](#), click on the button *Back*.
3. The window with the saved search settings appears.



Search Criteria


Chat

All

New Search ...

Fig. 44: Saved search settings (example)

4. Click on the line with the name of the saved search settings that you would like to use for the search.
  - ⇒ The window with the search criteria appears.
  - ⇒ The saved search settings are loaded in the window with the search criteria.



Search Criteria

Name of the search Chat

Conversation Information

Statistics of the Conversation

Calling Party Information

Called Party Information

1st-Connected Participant Information

General

Creation date between 11/01/2018 12:00 and 11/28/2018 2:18

Updated inactive



Additional Data


Search Reset Back

Fig. 45: Saved search settings loaded (example)

5. Click on the button *Search*.
  - ⇒ The found results are displayed in the main view.

#### 8.1.1.6.6 Delete saved search settings

1. In the toolbar, click on the icon  or  (*Search*).
2. If the window with the search criteria appears, see Fig. 39, p. 39, click on the button *Back*.
3. The window with the saved search settings appears.



Search Criteria

Chat

All

New Search ...

Fig. 46: Saved search settings (example)

4. Click on the line with the name of the saved search settings that you would like to delete.
  - ⇒ The window with the search criteria appears.
  - ⇒ The saved search settings are loaded in the window with the search criteria.







Fig. 47: Saved search settings loaded (example)

5. Click on the icon  on the right of the button *Back*.
6. Select the menu item *Delete* in the drop-down list.
  - ⇒ The saved search settings are deleted.

#### 8.1.1.6.7 Create search favorite

You can tag individual search criteria as favorites. Search favorites are displayed additionally in the upper area of the window *Search Criteria* and thus continue to be visible even if all criteria areas have been closed.

1. In the toolbar, click on the icon  or  (*Search*).
  - ⇒ If no saved search settings exist, the window with the search criteria appears, see [Fig. 39, p. 39](#).
  - ⇒ If the window with the saved search settings appears, implement one of the following steps:
    - If you would like to use one of the saved search settings, click on the line with the name of the saved search settings. The window of the search criteria appears. The saved search settings are loaded in the window with the search criteria.
    - If you do not want to use a saved search setting but define new search settings instead, click on the button *New Search*. The window of the search criteria appears.




Fig. 48: Saved search settings (example)

2. Set the respective search criteria, see [chapter "Search criteria", p. 37](#).

Search Criteria

Name of the search

Conversation Information

Statistics of the Conversation

Calling Party Information

Called Party Information

1st-Connected Participant Information

General

Creation date

between

11/01/2018 12:00

and

11/28/2018 2:18:00

☆

Updated

inactive

☆

Additional Data

Search

Reset

Back

Fig. 49: Enter search criteria (example)

- To tag one criterion as favorite, click on the icon ☆.
  - ⇒ The criterion tagged as favorite is displayed additionally in the upper area of the window and marked with the icon ☆.

Search Criteria

Name of the search

Chat

Creation date

between

11/01/2018 12:00

and

11/28/2018 1:26:00

☆

Conversation Information

Statistics of the Conversation

Calling Party Information

Called Party Information

1st-Connected Participant Information

General

Creation date

between

11/01/2018 12:00

and

11/28/2018 1:26:00

☆

Updated

inactive

☆

Additional Data

Search

Reset

Back

Fig. 50: Search criterion tagged as favorite (example)

- If you do not want to use a criterion tagged as favorite as a favorite anymore, click on the icon ☆.
  - ⇒ The criterion which is now no longer tagged as favorite is marked with the icon ☆.
  - ⇒ The criterion is no longer displayed in the upper area of the window.

Search Criteria
✕

Name of the search

---

▸ Conversation Information

---

▸ Statistics of the Conversation

---

▸ Calling Party Information

---

▸ Called Party Information

---

▸ 1st-Connected Participant Information

---

▼ General

---

Creation date

Updated

between

inactive

▼

▼

11/01/2018 12:00

and

11/28/2018 2:18:12

📅

📅

★

★

---

▸ Additional Data

---

^

[Search](#)
[Reset](#)

Back

▼

Fig. 51: Search criterion not tagged as favorite (example)

### 8.1.2 Change sort sequence

In their column headlines, some tables contain arrows which indicate the sort sequence and which allow you to change the sort sequence:

↕	No sorting
▼	Descending sort sequence
▲	Ascending sort sequence

Tab. 6: Main view - change sort sequence

To change the sort sequence of the table, click on the arrow in the column headline you would like to sort the table by.

## 8.2 Detail view

The detail view contains detailed information about the selected conversation in the main view.




Fig. 52: Detail view (example)

The detail view consists of the following tabs:

- **Details**  
Shows detailed information about the selected conversation.  
See [chapter "Tab Details", p. 46](#)
- **Participants**  
Shows participant information about the selected conversation.  
See [chapter "Tab Participants", p. 47](#).
- **Additional Data**  
Here, you can enter and edit additional data of the selected conversation.  
See [chapter "Tab Additional Data", p. 48](#)

The displayed information depend on the conversation type and on the selected module.

To change tabs, click on the tab you would like to display.

To open a group field, click on the arrow ► next to the name of the group field.

To hide a group field, click on the arrow ▼ next to the name of the group field.

When making changes, you can change tabs without buffering without risking the loss of the changes you have made.

To save changes, click on the button **Save**.

To discard the changes which have not yet been saved, click on the button **Reset**.

### 8.2.1

#### Tab Details

Shows detailed information about the selected conversation.

Details	Participants	Additional Data
Help		
<b>Conversation Information</b>		
Start time	11/20/2018 11:33:36 AM	
End time	11/20/2018 11:34:01 AM	
Data start	11/20/2018 11:33:39 AM	
Duration	00:00:24:784	
Conversation direction	Unknown	
Conversation ID	1d0e313a-188c-45b5-939a-87404ab66373	
DTMF sequence		
Conversation type	Call	
Archived	No	
Delete time	12/31/9999 12:00:00 AM	
<b>Statistics of the Conversation</b>		
Number of ringing sections	1	
Duration of ringing sections	00:00:01:410	
Number of hold sections	0	
Duration of hold sections	00:00:00:000	
Number of connected sections	1	
Duration of connected sections	00:00:23:374	
Number of failed callbacks	0	
Number of successful callbacks	0	
Conversation ID of callback request		
<b>Calling Party Information</b>		
Calling party PBX Agent ID		
Calling party phone number	user5	
Calling party name	Agent, 5.	
Employee number	500	
Device name		
<b>Called Party Information</b>		
Called party PBX Agent ID		
Called party phone number		
Called party name		
Employee number		
Device name		
<b>1st-Connected Participant Information</b>		
1st-connected PBX Agent ID		
1st-connected phone number		
1st-connected name		
Employee number		
Device name		

Fig. 53: Tab Details (example)

A description of the displayed information can be found in [chapter "Main view", p. 26](#). The displayed information in the detail view depends on the configuration of the columns in the main view.

## 8.2.2



### Tab Participants

Shows participant information about the selected conversation.

Details	Participants	Additional Data
Help		
<b>Participant View Information</b>		
Start time	11/20/2018 11:33:36 AM	
End time	11/20/2018 11:34:01 AM	
Data start	11/20/2018 11:33:39 AM	
Duration	00:00:24:784	
Call direction	Outgoing	
Comment		
Conversation ID	1d0e313a-188c-45b5-939a-87404ab66373	
Participant view ID	80980f91-34ca-4c14-b288-de1209228008	
DTMF sequence		
Conversation type	CALL	
Delete time	12/31/9999 12:00:00 AM	
<b>Statistics of the Conversation</b>		
Number of ringing sections	1	
Duration of ringing sections	00:00:01:410	
Number of hold sections	0	
Duration of hold sections	00:00:00:000	
Number of connected sections	1	
Duration of connected sections	00:00:23:374	
Number of failed callbacks	0	
Number of successful callbacks	0	
Conversation ID of callback request		
<b>Participant Information</b>		
PBX Agent ID		
Participant phone number	user5	
Participant name	Agent, 5.	
Device name		

Fig. 54: Tab Participants (example)

The following functions are available:


	No sorting
	Descending sort sequence

### Ascending sort sequence

To change the sort sequence of the table, click on the arrow in the column headline you would like to sort the table by.

## 8.2.3 Tab Additional Data

Here, you can enter and edit additional data of the selected conversation.




Additional Data	
Comment	0bf7a2b305b54c46869ea6232cabd3
Universal Call ID	09DDKF3B

Fig. 55: Tab Additional Data (example)

### 8.2.3.1 Enter or change additional data


1. Select the respective conversation in the main view.



Loaded	Conversation Type	Start Time	Data Start	End Time	Duration	Delete Time
	📞	12/16/2018 11:48:00 PM		12/16/2018 11:48:16 PM	00:00:16:469	12/30/9999 1:00:00 PM
	📞	12/16/2018 11:47:59 PM	12/16/2018 11:48:13 PM	12/16/2018 11:48:16 PM	00:00:16:922	12/30/9999 1:00:00 PM
	📞	12/16/2018 11:47:51 PM	12/16/2018 11:47:53 PM	12/16/2018 11:48:16 PM	00:00:25:268	12/30/9999 1:00:00 PM

Fig. 56: Select conversation (example)

2. Click on the tab *Additional data* in the detail view.



Additional Data	
Comment	0bf7a2b305b54c46869ea6232cabd3
Universal Call ID	09DDKF3B

Fig. 57: Tab Additional Data (example)

3. Enter the additional data for the conversation in an editable entry field, e. g. in the entry field *Comment*.
4. Click on the button *Save*.
  - ⇒ Depending on the configuration of the columns, information is displayed in the main view:



## 9

## Recording View module

The Recording View module is only available with an Airbus PBX.

The Recording View module opens the recordings of all active participants in a table. A recording is a conversation segment that 1 participants actively participates in. Exclusively those conversation segments are considered that have taken place from the moment on a connection has been established between the participants (connect section). I. e. for two conversation participants two recordings (one for the calling party and one for the called party) are displayed in the table. These recordings have the same section ID but different active participants.

## 9.1

## Main view

The main view of the Recording View module shows all recordings.



When opening the module, a search filter is set automatically so that only data sets of the last 14 days are displayed.

The function *Reset search* (🔄) does not deactivate this filter!

Click on the icon (🔍) (Search) to adjust the search filter to your requirements.



If conversation rules (view filters) apply for the logged-in user, then the main view only contains those entries which comply with these conversation rules.

<div> <span>🔄</span> <span>🔍</span> Recording View ▾ General ▾ </div>					
Loaded ▾	Section ID ▾	Start Time ▾	End Time ▾	Duration ▾	
	fb872f80-d5e5-4d21-aa5e-50397f0337a3	11/20/2018 11:33:55 AM	11/20/2018 11:34:28 AM	00:00:33:557	
	fb872f80-d5e5-4d21-aa5e-50397f0337a3	11/20/2018 11:33:55 AM	11/20/2018 11:34:28 AM	00:00:33:557	
	fb872f80-d5e5-4d21-aa5e-50397f0337a3	11/20/2018 11:33:55 AM	11/20/2018 11:34:28 AM	00:00:33:557	
	fb872f80-d5e5-4d21-aa5e-50397f0337a3	11/20/2018 11:33:55 AM	11/20/2018 11:34:28 AM	00:00:33:557	
	4a50c227-702e-46d5-8e20-7328f186127b	11/20/2018 11:33:37 AM	11/20/2018 11:34:01 AM	00:00:23:374	
	4a50c227-702e-46d5-8e20-7328f186127b	11/20/2018 11:33:37 AM	11/20/2018 11:34:01 AM	00:00:23:374	
	4a50c227-702e-46d5-8e20-7328f186127b	11/20/2018 11:33:37 AM	11/20/2018 11:34:01 AM	00:00:23:374	
	4028cdb9-395a-4860-ad6e-b0611f1a94e3	11/20/2018 11:33:22 AM	11/20/2018 11:34:27 AM	00:01:04:881	
	4028cdb9-395a-4860-ad6e-b0611f1a94e3	11/20/2018 11:33:22 AM	11/20/2018 11:34:27 AM	00:01:04:881	
	4028cdb9-395a-4860-ad6e-b0611f1a94e3	11/20/2018 11:33:22 AM	11/20/2018 11:34:27 AM	00:01:04:881	
<div> Rows per page 50 ▾ 1 - 50 of 1000 <div> <span>⏪</span> <span>⏩</span> </div> Last filtered on 11/28/2018 8:01:51 AM; Number of known datasets: 1000 </div>					

Fig. 58: Main view Recording View (example)

Depending on the configuration of the columns, the following information is displayed in the main view:

## General

## Loaded

Shows whether the recording has been loaded in the Replay module.



= Recording has not been loaded.



= Recording has been loaded.

The loaded recording is assigned a color from a defined color palette. The order of the colors has been predetermined. If all colors of a palette have been used for several recordings, the color assignment starts from the beginning again. In the Replay module, the loaded recording is displayed in the same color.

#### Conversation Information

<i>Section ID</i>	Shows the ID of the section that the recording belongs to.
<i>Start Time</i>	Shows when the section that the recording belongs to started.
<i>End Time</i>	Shows when the section that the recording belongs to ended.
<i>Creation Date</i>	Shows when the recording was created.
<i>Updated</i>	Shows when the recording was updated for the last time.
<i>Duration</i>	Shows the duration of the section.
<i>Deletion Time</i>	Shows when the recording is deleted automatically.

#### Statistics of the Conversation

<i>Number of Connected Sections</i>	Shows the number of connected sections.
<i>Duration of Connected Sections</i>	Shows the duration of the connected sections.
<i>Number of Failed Callbacks</i>	Shows the number of failed callbacks.
<i>Number of Successful Callbacks</i>	Shows the number of successful callbacks.
<i>Conversation ID of Callback Request</i>	Shows the conversation ID of the callback request.

#### Calling Party Information

<i>Calling Party Name</i>	Shows the name of the calling party (last name, first name).
<i>Calling Party PBX Agent ID</i>	Shows the PBX Agent ID of the calling party.
<i>Calling Party Phone Number</i>	Shows the phone number of the calling party.
<i>Calling Party Device Name</i>	Shows the device name of the turret or of the phone of the calling party.

#### Called Party Information

<i>Called Party Name</i>	Shows the name of the called party (last name, first name).
<i>Called Party PBX Agent ID</i>	Shows the PBX Agent ID of the called party.
<i>Called Party Phone Number</i>	Shows the phone number of the called party.
<i>Called Party Device Name</i>	Shows the device name of the turret or of the phone of the called party.

#### 1st-Connected Participant Information

<i>1st-Connected Name</i>	Shows the name of the 1st connected (last name, first name).
<i>1st-Connected PBX Agent ID</i>	Shows the PBX Agent ID of the 1st connected.

<i>1st-Connected Phone Number</i>	Shows the phone number of the 1st connected.
<i>1st-Connected Device Name</i>	Filters for the device name of the turret or of the phone of the 1st connected.

#### Active Participant Information

<i>Active Participant Name</i>	Shows the name of the active participant (last name, first name).
<i>Active Participant PBX Agent ID</i>	Shows the PBX Agent ID of the active participant.
<i>Active Participant Phone Number</i>	Shows the phone number of the active participant.
<i>Active Participant Device Name</i>	Shows the device name of the turret or of the phone of the active participant.

#### Additional Data

<i>Display Name Additional Data</i>	Shows the additional conversation data. You have to have the respective rights to be able to display the additional data. For information about the configuration of the additional data refer to the administration manual <i>System Configuration - Additional Data module</i> .
-------------------------------------	--

Information about the configuration of the table can be found in [chapter "Adjust table", p. 35](#).





The toolbar of the main view contains all functions which can be used for the elements of the main view, see [chapter "Toolbar", p. 51](#).

The sort sequence of the table can be adjusted arbitrarily, see [chapter "Change sort sequence", p. 54](#).

At the bottom edge of the main view, buttons allow you to browse the pages of the main view and indicate which page you are on.

51 - 100 of 298    ◀ ◀ ▶ ▶

Fig. 59: Changing pages

	Jumps to the first page of the main view.
	Jumps to the previous page of the main view.
51 - 100 of 298	Shows the range of the displayed sets of data on the current page of the main view.
	Jumps to the next page of the main view.
	Jumps to the last page of the main view.

On the pages of the main view, you can navigate by using the scrollbars.


### 9.1.1 Toolbar





The toolbar of the main view is located in the center window and offers different functions.



Fig. 60: Toolbar Recording View

In the following, you find a description of the icons.

	<i>Refresh</i>	Refreshes the table in the main view.
---	----------------	---------------------------------------

 	<i>Search</i>	<p>Opens the window of the search function. The search function allows searching systematically for sets of data which meet certain criteria, see <a href="#">chapter "Search", p. 36</a>.</p> <p>When opening the module, a search filter is set automatically so that only data sets of the last 14 days are displayed. The function by means of the icon  (<i>Reset search</i>) does not deactivate this filter!</p> <p>The icon  (<i>Search</i>) is displayed whenever the search has been adjusted by means of a filter.</p>
	<i>Reset search</i>	Resets all manually entered search criteria. The search is started without manual filter settings.
	<i>Count results</i>	<p>Determines the number of data sets according to the current list of search results in the main view.</p> <p>The number of data sets is displayed at the bottom of the main view, see pos. 11 in <a href="#">Fig. 12, p. 15</a>.</p>
	<i>Load selected recording</i>	Loads a selected recording into the Replay module for replay, see <a href="#">chapter "Load selected recording", p. 52</a> .
<i>Recording View</i>	<i>Export</i>	Saves the audio data of the selected recording as <b>WAVE</b> file and the corresponding additional data as CSV file on the hard disk of your computer, see <a href="#">chapter "Export recording", p. 53</a> .
<i>General</i>	<i>Adjust Table</i>	Opens the window <i>Table Configuration</i> , see <a href="#">chapter "Adjust table", p. 35</a> .
	<i>General Help</i>	By clicking on the menu item <i>General Help</i> , a description of the application you are currently viewing is opened. See <a href="#">chapter "Call up online help", p. 20</a> .
	<i>Module Help</i>	By clicking on the menu item <i>Module Help</i> , a description of the module you are currently viewing is opened. See <a href="#">chapter "Call up online help", p. 20</a> .





It depends on your function rights which of the described functions are available.

### 9.1.1.1

#### Load selected recording

This function allows loading recordings into the Replay module and replaying them there.

- In the main view, select the element you would like to replay.  
To select several elements or to revoke the selection, click on the respective line while holding the [Ctrl] key down.  
**NOTICE!** If you would like to select several elements, the earliest start time and the latest end time must not be more than 24 hours apart.
- Click on the icon  (*Load selected recording*).



Loaded	Section ID	Start Time	End Time	
	fb872f80-d5e5-4d21-aa5e-50397f0337a3	11/20/2018 11:33:55 AM	11/20/2018 11:34:28 AM	00:00:33:557
	fb872f80-d5e5-4d21-aa5e-50397f0337a3	11/20/2018 11:33:55 AM	11/20/2018 11:34:28 AM	00:00:33:557
	fb872f80-d5e5-4d21-aa5e-50397f0337a3	11/20/2018 11:33:55 AM	11/20/2018 11:34:28 AM	00:00:33:557

Fig. 61: Load selected recording

- Select the option *Load selected recording* to load the recording into the Replay module.

- ⇒ The recordings are loaded into the Replay module and can be replayed there.  
For information about the functions of the Replay module see [chapter "Replay module", p. 59](#).



A recording can also be loaded into and replayed in the Replay module by double-clicking on the element in the main view.

### 9.1.1.2


#### Export recording

- In the main view, select the recording you would like to export.  
To select several recording or to cancel a selection, hold the [Ctrl] key down and click on the respective line.

Loaded ↕	Section ID ↕	Start Time ↕	End Time ↕	Duration ↕
	fb872f80-d5e5-4d21-aa5e-50397f0337a3	11/20/2018 11:33:55 AM	11/20/2018 11:34:28 AM	00:00:33:557
	fb872f80-d5e5-4d21-aa5e-50397f0337a3	11/20/2018 11:33:55 AM	11/20/2018 11:34:28 AM	00:00:33:557
	fb872f80-d5e5-4d21-aa5e-50397f0337a3	11/20/2018 11:33:55 AM	11/20/2018 11:34:28 AM	00:00:33:557

Fig. 62: Select recording

- Click on the menu item *Conversations > Export* in the toolbar of the main view.  
⇒ The following window appears:



**Save As**  
Select whether you would like to export one file or several files

☒ **One**  
☐ **Several**  
☐ **Fragment**

Select the media to be exported

☐ **Audio** PCM Wave ▾  
☐ **Video**  
☐ **Screen**  
☐ **Chat**  
☐ **SMS**

You can enter an optional password to protect the ZIP file

**Password**   
**Password**

OK Cancel

Fig. 63: Save as

- Select the respective option in the window *Save As*.

<i>Single</i>	Mixes all recordings of one or several conversations in one file.
<i>Several</i>	Creates its own file for each recording to be saved.
<i>Fragment</i>	Only data contained in the set loop are saved. All other data is discarded.
<i>Audio</i>	Saves the audio data. Select the audio format from the drop-down list: <ul style="list-style-type: none"> <li>• <i>PCM Wave</i></li> </ul>

With **PCM**, the output file is not compressed and can be replayed by almost any player. This method requires a lot of storage capacity.

- **MP3**

With **MP3**, the output file is compressed and can be replayed by almost any player. This method requires less storage capacity.

<b>Video</b>	Saves the <b>video data</b> .
<b>Screen</b>	Saves the screen recordings.
<b>Chat</b>	Saves the chat text.
<b>SMS</b>	Saves the SMS data.

**Password** Protects the ZIP file with a password.

- Click on the button **OK**.

⇒ The following window appears:




Fig. 64: Save conversations

- Select the option **Save File**.

- Click on the button **OK**.

⇒ The elements are exported to the local download directory in a ZIP file.

The ZIP file contains the following files:

The audio data is saved as **WAVE** file(s).

Audio data and screen recordings are saved as **MP4** file(s).

Video data is saved as **MP4** file(s).

Screen data is saved as **MP4** file(s).

The corresponding meta data is saved in the same directory as **CSV** file(s) under the same file name.

Chat texts are saved as **XML** file(s).

SMS data is saved as **XML** file(s).

### 9.1.2 Change sort sequence

In their column headlines, some tables contain arrows which indicate the sort sequence and which allow you to change the sort sequence:


	No sorting
	Descending sort sequence
	Ascending sort sequence

Tab. 7: Main view - change sort sequence

To change the sort sequence of the table, click on the arrow in the column headline you would like to sort the table by.

## 9.2 Detail view

The detail view contains detailed information about the selected recording in the main view.



Recording View	
<div> <div>Details</div> <div>Participants</div> <div>Additional Data</div> </div> <div>Help</div>	
Start time	11/20/2018 11:33:55 AM
End time	11/20/2018 11:34:28 AM
Duration	00:00:33:557
Active participant name	
Device name	
Delete time	12/31/9999 12:00:00 AM
Statistics of the Conversation	
Calling Party Information	
Called Party Information	
1st-Connected Participant Information	
<div>Save</div> <div>Reset</div>	

Fig. 65: Detail view (example)

The detail view consists of the following tabs:

- *Details*  
Shows detailed information about the selected recording.  
See [chapter "Tab Details", p. 56](#)
- *Participants*  
Shows participant information about the selected recording.  
See [chapter "Tab Participants", p. 57](#).
- *Additional Data*  
Here, you can enter and edit additional data of the selected recording.  
See [chapter "Tab Additional Data", p. 57](#)

To change tabs, click on the tab you would like to display.

To open a group field, click on the arrow ► next to the name of the group field.

To hide a group field, click on the arrow ▼ next to the name of the group field.

When making changes, you can change tabs without buffering without risking the loss of the changes you have made.

To save changes, click on the button *Save*.

To discard the changes which have not yet been saved, click on the button *Reset*.

### 9.2.1

#### Tab Details

Shows detailed information about the selected recording.

<

Details
Participants
Additional Data

Help

Start time	11/20/2018 11:33:55 AM
End time	11/20/2018 11:34:28 AM
Duration	00:00:33:557
Active participant name	
Device name	
Delete time	12/31/9999 12:00:00 AM

Statistics of the Conversation

Number of connected sections	1
Duration of connected sections	00:00:33:557
Number of failed callbacks	0
Number of successful callbacks	0
Conversation ID of callback request	

Calling Party Information

Calling party PBX Agent ID	
Calling party phone number	user8
Calling party name	Agent, 8.
Device name	

Called Party Information

Called party PBX Agent ID	
Called party phone number	user11
Called party name	
Device name	

1st-Connected Participant Information

1st-connected PBX Agent ID	
1st-connected phone number	user11
1st-connected name	
Device name	

Fig. 66: Tab Details (example)



A description of the displayed information can be found in [chapter "Main view", p. 49](#). The displayed information in the detail view depends on the configuration of the columns in the main view.




### 9.2.2 Tab Participants

Shows participant information about the selected recording.

<div> <div>&lt;</div> <div>Details</div> <div>Participants</div> <div>Additional Data</div> <div>&gt;</div> </div>			
Type ↕	Phone Number ↕	PBX Agent ID ↕	Time Slot ID ↕
[*]	user8		
]*[	user11		

Fig. 67: Tab Participants (example)

The following functions are available:

	No sorting
	Descending sort sequence
	Ascending sort sequence

To change the sort sequence of the table, click on the arrow in the column headline you would like to sort the table by.

### 9.2.3 Tab Additional Data

Here, you can enter and edit additional data of the selected recording.

<div> <div>&lt;</div> <div>Details</div> <div>Participants</div> <div>Additional Data</div> <div>&gt;</div> </div>	
Additional Data	
Comment	0bf7a2b305b54c46869ea6232cabd3
Universal Call ID	09DDKF3B

Fig. 68: Tab Additional Data (example)

#### 9.2.3.1 Enter or change additional data

1. Select the respective conversation in the main view.




<div> <div>↺</div> <div>↻</div> <div>×</div> <div>Conversations</div> <div>General</div> </div>						
Loaded	Conversation Type ↕	Start Time ↕	Data Start ↕	End Time ↕	Duration ↕	Delete Time
		12/16/2018 11:48:00 PM		12/16/2018 11:48:16 PM	00:00:16:469	12/30/9999 1:00:00 PM
		12/16/2018 11:47:59 PM	12/16/2018 11:48:13 PM	12/16/2018 11:48:16 PM	00:00:16:922	12/30/9999 1:00:00 PM
		12/16/2018 11:47:51 PM	12/16/2018 11:47:53 PM	12/16/2018 11:48:16 PM	00:00:25:268	12/30/9999 1:00:00 PM

Fig. 69: Select conversation (example)

2. Click on the tab *Additional data* in the detail view.

<

Details

Participants

Additional Data

>

Additional Data

Comment

0bf7a2b305b54c46869ea6232cabd3

Universal Call ID

09DDKF3B

Fig. 70: Tab Additional Data (example)

3. Enter the additional data for the conversation in an editable entry field, e. g. in the entry field *Comment*.
4. Click on the button *Save*.
  - ⇒ Depending on the configuration of the columns, information is displayed in the main view:

## 10 Replay module

The Replay module serves to replay conversations. Conversations which are supposed to be replayed must be selected in the main view and loaded into the Replay module.

If conversations with screen or camera recordings are loaded into the Replay module, the window of the Video Viewer opens automatically for replaying the [video recording](#), see [chapter "Video Viewer", p. 72](#). The replay functions are executed synchronously for the conversation in the Replay module and for the video recording in the Video Viewer.

If conversations with chat texts or text messages (SMS or SDS) are loaded into the Replay module, the window of the Message Viewer opens automatically for displaying the chat texts or the text messages recording, see [chapter "Message Viewer", p. 75](#).





Fig. 71: Welcome screen (example)

1	Replay bar	Shows the loaded conversations, see <a href="#">chapter "Replay bar", p. 59</a> .
2	Functionality bar	Contains functionalities for the loaded conversations in the replay bar, see <a href="#">chapter "Functionality bar", p. 62</a> .

### 10.1 Replay bar

The replay bar shows the loaded conversations.

In the replay bar, there are 2 different views: the full view and the compressed view. To switch the view, go to the functionality bar on the right and click on the icon  (Switch to full view) or  (Switch to compressed view).




Fig. 72: Replay bar in the full view









Fig. 73: Replay bar in compressed view

1	Shows the start time of the loaded conversation. If several conversations have been loaded in 1 track, the start time of the earliest conversation is displayed here.
2	Displays information about the conversation participants. The information is only visible when the replay bar is displayed in full view.  = internal participants  = external participants  = mixed track with internal and external participants  = unknown participants  = screen recording To display the phone numbers of the participants in one track, move the mouse cursor across the participants icon.
3	Displays track 1 of a loaded conversation. For further information see <a href="#">chapter "Display of the loading states", p. 61</a> .
4	Shows the replay position. To change the current replay position of the loaded conversation, you have 2 possibilities: 1. Click on the respective replay position. 2. Click on a track, hold the mouse key down and drag the cursor to the left or to the right.
5	Shows the sections of the conversation. The following sections are possible: <ul style="list-style-type: none"> <li>• R = Ringing (a connection is being established)</li> <li>• C = Connected (at least 2 participants are calling each other)</li> <li>• H = Hold (a participant is on hold)</li> <li>• Q = Queued (a participant has been queued)</li> <li>• W = Wrap-up (wrap-up time)</li> </ul>
6	Shows tagging and audio analysis data (e. g. found keywords). The line is only displayed if information is available.
7	Shows the end time of the loaded conversation. If several conversations have been loaded in 1 track, the end time of the last conversation is displayed here.
8	Displays track 2 of a loaded conversation. For further information see <a href="#">chapter "Display of the loading states", p. 61</a> .

### 10.1.1 Full view

In the full view, all tracks for voice and screen recording which belong to the loaded conversation are displayed in the replay bar of the Replay module.

When replaying stereo recordings with several internal participants, an echo effect occurs because the voices of some participants have been recorded several times. To avoid the echo effect, tracks with double recording have to be muted.

### 10.1.2 Compressed view

In the compressed view, no individual tracks for voice and screen recording are displayed in the replay bar of the Replay module. All recordings of a loaded conversation are combined in one group within one track.

In the compressed view, double recordings are suppressed automatically to avoid echo effects. If errors occur during recording, display the replay bar in full view and mute the single tracks manually.

### 10.1.3 Display of the loading states

The loaded conversation is assigned a basic color from a defined color palette.

The replay bar of the conversation shows its loading state. In the following, you find a description of the possible loading states.

1. Basis color (e. g. light brown) = Meta data loaded completely.

⇒ The conversation can be replayed.



Fig. 74: Meta data loaded completely

2. Empty = Meta data for the recording are missing.

⇒ The conversation cannot be replayed.



Fig. 75: Meta data for the recording is missing

3. Red striped basic color (only in full view) = Audio data of the recording is defective.

⇒ The conversation cannot be replayed.



Fig. 76: Defective packet in the meta data of the recording (full view)

4. Red dotted basic color (only in full view) = Packet in the meta data of the recording is missing.

⇒ The conversation cannot be replayed.



Fig. 77: Missing packet in the meta data of the recording (full view)

5. Red exclamation mark (only in compressed view) = Audio data of the recording is defective or packet in the meta data of the recording is missing.

For a more precise specification of the diagram change to the full view.

⇒ The conversation cannot be replayed.



Fig. 78: Defective or missing packet in the meta data of the recording (compressed view)

6. Basic color, light (e. g. ocher, light) = Data buffer empty.

Basic color (e. g. ocher) = Data buffer loaded.

⇒ The conversation can be replayed. An empty data buffer is reloaded automatically. If the server connection is slow, the replay may stop. As soon as the data buffer has been reloaded, the replay continues.



Fig. 79: Data buffer empty/loading

7. Red = Data buffer not loaded completely.

⇒ The conversation is defective and cannot be replayed.




Fig. 80: Data buffer not loaded completely

8. Basis color (e. g. light brown) = Meta data loaded completely.  
Red = Data buffer not loaded completely.
  - ⇒ In the basic color section, the conversation can be replayed.
  - ⇒ In the red section, the conversation is defective and cannot be replayed.




Fig. 81: Data buffer not loaded completely

9. Purple = Packet is muted during the recording.
  - ⇒ The conversation can be replayed. There is nothing to be heard since no audio data has been recorded. Packets which have once been muted are muted permanently and cannot be changed afterwards.




Fig. 82: Packet is muted during the recording

10. Basis color (e. g. light brown) = Meta data loaded completely.  
Purple, light = Conversation section muted
  - ⇒ The conversation can be replayed. In the muted conversation section, silence is replayed. The muted conversation section can be deleted so that the audio data can be replayed.



Fig. 83: Conversation section muted

11. Gray = The recording contains data which is not supported.
  - ⇒ The conversation cannot be replayed.



Fig. 84: The recording contains data which is not supported.

#### 10.1.4 Display of detected emotions

If an emotion detection job has found emotions in a conversation, the event indicating an emotion is marked in the loaded conversation in a certain color depending on the event type. The position and length of the markings coincide with the occurrence and the duration of the event indicating an emotion in the conversation.



Fig. 85: Emotions detected in a conversation (example)

In the following, you find a description of the possible color markings:

















- Light blue indicates a section of silence.
- Red indicates a section of noise.
- Yellow indicates a section of cross talk or of massive cross talk.
- Green indicates unsuspecting audio sections.


















#### 10.2 Functionality bar

The functionality bar contains functionalities for the loaded conversations in the replay bar.


### 10.2.1 Icons

In the following, you find a description of the icons.

	<i>Play/ Pause</i>	Starts the replay.  If several conversations have been loaded into the Replay module, the conversations may be replayed in parallel if the recording times overlap.
		Pauses the replay.
	<i>Stop</i>	Stops the replay.
	<i>Rewind</i>	Jumps back 5 seconds from the current replay position.
	<i>Back</i>	Jumps to the start of the current or of the previous conversation.
	<i>Fast-forward</i>	Jumps ahead 5 seconds from the current replay position.
	<i>Next</i>	Jumps to the start of the next conversation.
	<i>Lock element</i>	Shows that the lock for the Replay module has been deactivated. As a result, several conversations can be loaded into the Replay module.  <b>Note:</b> In principle, you can load several video recordings into the Video Viewer. However, you can only replay one of them at any given moment.
		Shows that the lock for the Replay module has been activated. As a result, only one conversation can be loaded into the Replay module.
	<i>Reconnect to the replay component</i>	Refreshes the server connection.
	<i>Display video window</i>	Shows the Video Viewer in the main view of the application.
	<i>Hide video window</i>	Shows the main view of the application. The Video Viewer integrated into the main view is hidden.
	<i>Detach Video Viewer</i>	Displays the Video Viewer in its own window.
	<i>Attach Video Viewer</i>	Closes the window of the Video Viewer.
	<i>Unmute/Mute</i>	Shows that the speaker for the conversation has been activated.
		Shows that the speaker for the conversation has been deactivated.

	<i>Volume</i>	<p>Adjusts the general replay volume.</p> <p>To change the volume, click on the slider, hold the mouse key down and move the slider to the left or to the right.</p>
	<i>Clear playlist</i>	Removes all loaded conversations from the Replay module.
	<i>Export all loaded elements</i>	Saves the audio data of the loaded conversations as <a href="#">WAVE</a> file and the corresponding additional conversation data as CSV file on the hard disk of your computer, see <a href="#">chapter "Export all loaded elements", p. 65</a> .
	<i>Create new bookmark</i>	Sets a bookmark or marks the beginning of a conversation section at the current replay position, see <a href="#">chapter "Create new bookmark", p. 67</a> .
		Sets a bookmark or marks the end of a conversation section at the current replay position. You can enter a comment for the marked area between the 2 associated bookmarks, see <a href="#">chapter "Create new bookmark", p. 67</a> .
	<i>Create new mute notification</i>	Marks the beginning of a conversation section at the current replay position in order to mute selected participants, see <a href="#">chapter "Create new mute notification", p. 70</a> .
		Marks the end of a conversation section at the current replay position in order to mute selected participants, see <a href="#">chapter "Create new mute notification", p. 70</a> .
	<i>Loop</i>	Marks the beginning of a replay loop at the current replay position, see <a href="#">chapter "Mark replay loop", p. 72</a> .
		Marks the end of a replay loop at the current replay position, see <a href="#">chapter "Mark replay loop", p. 72</a> .
		Removes the taggings of the replay loop, see <a href="#">chapter "Mark replay loop", p. 72</a> .
	<i>Skip silence</i>	Shows that the automatic skipping of times of silence between individual conversations has been deactivated.
		Shows that the automatic skipping of times of silence between individual conversations has been activated.
		<p>Shows the current replay speed.</p> <p>The replay speed can be adjusted between 0.5 and 2.0.</p> <p>To reduce the replay speed, click on the icon  <i>Reduce replay speed</i>.</p> <p>To increase the replay speed, click on the icon  <i>Increase replay speed</i>.</p>
	<i>Replay via phone</i>	Shows that the conversation replay via phone has been deactivated.
		Shows that the conversation replay via phone has been activated.



To replay loaded conversations, click on the icon  (Play).

1 Minute 

Shows the time window for the loaded conversations.

You can enter the time window in 25 steps from 1 second to 14 days. There are 2 possibilities to change the time window:

1. On the right in the time window, click on + or -.
2. Turn the mouse wheel while the mouse cursor is located above the replay track.

20.11.2018 11:33:36

Shows the current replay position.

Click into the display field to switch from absolute to relative time display and vice versa.

The absolute time display shows the date and the time of the current replay position.

The relative time display shows the replayed time until the current replay position in HH:MM:SS.

Icons in the functionality bar on the right



Expanded view

Switches the replay bar to full view.



Simple view

Switches the replay bar to compressed view.

Icons in the functionality bar on the left



Display toolbar

Shows all icons in the functionality bar



Hide toolbar

Partly hides the icons in the functionality bar.



Not all described icons exist in every module and application.

### 10.2.2

#### Export all loaded elements

1. Click on the icon  (*Export all loaded elements*).

⇒ The following window appears:




Fig. 86: Save as

2. Select the respective option in the window *Save As*.

<i>Single</i>	Mixes all recordings of one or several conversations in one file.
<i>Several</i>	Creates its own file for each recording to be saved.
<i>Fragment</i>	Only data contained in the set loop are saved. All other data is discarded.
<i>Audio</i>	<p>Saves the audio data.</p> <p>Select the audio format from the drop-down list:</p> <ul style="list-style-type: none"> <li>• <i>PCM Wave</i> <p>With <b>PCM</b>, the output file is not compressed and can be replayed by almost any player. This method requires a lot of storage capacity.</p> </li> <li>• <i>MP3</i> <p>With <b>MP3</b>, the output file is compressed and can be replayed by almost any player. This method requires less storage capacity.</p> </li> </ul>
<i>Video</i>	Saves the <b>video data</b> .
<i>Screen</i>	Saves the screen recordings.
<i>Chat</i>	Saves the chat text.
<i>SMS</i>	Saves the SMS data.
<i>Password</i>	Protects the ZIP file with a password.

3. Click on the button *OK*.
  - ⇒ The following window appears:




Fig. 87: Save conversations

4. Select the option *Save File*.
5. Click on the button *OK*.
  - ⇒ The elements are exported to the local download directory in a ZIP file.  
 The ZIP file contains the following files:  
 The audio data is saved as **WAVE** file(s).  
 Audio data and screen recordings are saved as MP4 file(s).  
 Video data is saved as MP4 file(s).  
 Screen data is saved as MP4 file(s).  
 The corresponding meta data is saved in the same directory as CSV file(s) under the same file name.  
 Chat texts are saved as **XML** file(s).  
 SMS data is saved as **XML** file(s).

### 10.2.3 Create new bookmark

The intention is not to create only one single bookmark. The beginning and the end of a conversation section have to be marked with a new bookmark. You can enter a replay comment for this tagged conversation section between 2 bookmarks.

In a conversation, several conversation sections can be marked with bookmarks and commented.




---

It is not possible to delete only 1 bookmark from a tagged conversation section.

---



#### 10.2.3.1 Create bookmarks with replay comment




---

The current replay position has to be located within the conversation.

---

1. To mark the beginning of a conversation section for a replay comment, click on the icon  (*Create new bookmark*).
2. To mark the end of a conversation section for a replay comment, click on the icon  (*Create new bookmark*).
  - ⇒ The following window appears:




Fig. 88: Tagging editor

<b>OK</b>	Saves the entries and closes the window.
<b>Cancel</b>	Discards the entries and closes the window.

3. Enter a comment for the conversation in the entry field.



Fig. 89: Tagging editor with entered comment (example)

4. To save the entries, click on the button **OK**.
  - ⇒ The tagged conversation section is displayed in other color above the replay bar.
  - ⇒ When replaying the conversation, the information details are displayed in the area of the tagging.



Fig. 90: Conversation with tagged conversation section (example)




Fig. 91: Displayed information details (example)

### 10.2.3.2 Edit bookmarks with replay comment

1. As soon as the tagged conversation section with the replay comment is located above the replay position, the following window appears:





Fig. 92: Displayed information details (example)

2. Click on the icon  (Edit).  
⇒ The following window appears:






Fig. 93: Edit tagging (example)

	Saves the entries and closes the window.
	Discards the entries and closes the window.

3. Edit the replay comment.
4. To save the entries, click on the button **OK**.

### 10.2.3.3 Delete bookmarks with replay comment

1. As soon as the tagged conversation section with the replay comment is located above the replay position, the following window appears:





Fig. 94: Displayed information details (example)

2. Click on the icon  (Delete).  
To delete the tagged conversation area with the replay comment, confirm the security prompt.

### 10.2.4 Create new mute notification

The intention is not to create only one single mute notification. The beginning and the end of a conversation section have to be marked with a new mute notification. This tagged conversation section between 2 mute notifications can be muted for selected participants.

In a conversation, several conversation sections can be marked with mute notifications and selected participants can be muted.





It is not possible to delete only one mute notification from a tagged conversation section which marks the beginning or the end.

#### 10.2.4.1 Mute conversation section



The current replay position has to be located within the conversation.

1. To mark the beginning of a conversation section for the muting of selected participants, click on the icon  (*Create new mute notification*).
2. To mark the end of a conversation section for the muting of selected participants, click on the icon  (*Create new mute notification*).  
⇒ The following window appears:






Fig. 95: Muting for selected participants (example)

	Saves the entries and closes the window.
	Discards the entries and closes the window.

3. Select the participants for whom the conversation section is supposed to be muted. At least 1 participant has to be muted.  
☒ = Conversation muted for participant  
☐ = Conversation not muted for participant
4. To save the entries, click on the button **OK**.  
 ⇒ The muted conversation section is displayed as a gray area in the replay bar.  
 ⇒ When replaying the conversation, the mute section details are displayed in the area of the muting.




Fig. 96: Conversation with muted conversation section (example)




Fig. 97: Displayed mute section details (example)

#### 10.2.4.2 Edit muted conversation section

1. As soon as the muted conversation section is located above the replay position, the following window appears:





Fig. 98: Mute Section Details (example)

2. Click on the icon  (Edit).  
⇒ The following window appears:






Fig. 99: Edit mute section (example)

	Saves the entries and closes the window.
	Discards the entries and closes the window.

3. Select the participants for whom the conversation section is supposed to be muted. At least 1 participant has to be muted.  
☒ = Conversation muted for participant  
☐ = Conversation not muted for participant
4. To save the entries, click on the button **OK**.

#### 10.2.4.3 Delete muted conversation section

1. As soon as the muted conversation section is located above the replay position, the following window appears:





Fig. 100: Mute Section Details (example)

2. Click on the icon  (*Delete*).  
To delete the mute section, confirm the security prompt.

### 10.2.5 Mark replay loop




1. To mark the beginning of a replay loop at the current replay position, click on the icon  (*Loop*).
2. To mark the end of a replay loop at the current replay position, click on the icon  (*Loop*).  
⇒ When the replay is started, the area between the marks is replayed in an endless loop.
3. To remove the marks of the replay loop, click on the icon  (*Loop*).



Fig. 101: Conversation with replay loop

## 10.3 Video Viewer

The Video Viewer serves to replay screen and camera recordings (video recordings).







In principle, you can load several video recordings into the Video Viewer. However, you can only replay one at any given moment.





Fig. 102: Video Viewer (example)

1	Option bar	Contains settings for displaying video recordings, see <a href="#">chapter "Option bar", p. 74.</a>
2	Main view	Shows the <a href="#">Video recording</a> .
3	Replay bar	Shows the loaded video recordings, see <a href="#">chapter "Replay bar", p. 74.</a>
4	Functionality bar	Contains functionalities for the loaded conversations in the replay bar, see <a href="#">chapter "Icons", p. 63.</a> In the Video Viewer, not all icons of the Replay module are available.
5	 (Minimize)	Minimizes the on-screen display to the program icon in the taskbar.
6	 (Maximize)	Maximizes the on-screen display to full-screen size.
	 (Reconstruct)	Reduces the on-screen display to the most recently selected reduced window size.

- 7  Closes the window of the Video Viewer.  
(Close)

### 10.3.1 Option bar

The option bar contains settings for displaying video recordings.



Fig. 103: Option bar

In the following, you find a description of the settings.

<b>Aspect ratio</b>	<p>This option is only active if <i>Adjust to Window</i> has been activated upon setting the video size. When setting the video size to <i>Original</i> and <i>User-Defined</i>, the setting <i>Aspect ratio</i> is deactivated.</p> <ul style="list-style-type: none"> <li>• <i>Keep</i> The original aspect ratio of the <a href="#">video recording</a> remains unchanged in the window of the main view of the Video Viewer.</li> <li>• <i>Ignore</i> The display of the <a href="#">video recording</a> is adjusted to the window size of the main view of the Video Viewer. The aspect ratio is ignored, i. e. the display may be distorted.</li> <li>• <i>Original</i> The <a href="#">video recording</a> is displayed in its original size in the main view of the Video Viewer.</li> </ul>
---------------------	--

### 10.3.2 Replay bar

The replay bar shows the loaded video recordings.




Fig. 104: Replay bar

- Shows the track of a loaded [video recording](#).
- Shows the start time of the loaded conversation.  
If several conversations have been loaded in 1 track, the start time of the earliest conversation is displayed here.
- Shows that this is the track of a [video recording](#).
- Shows the replay position.  
To change the current replay position of the loaded conversation, you have 2 possibilities:
  - Click on the respective replay position.
  - Click on a track, hold the mouse key down and drag the cursor to the left or to the right.
- Shows the sections of the conversation.  
The following sections are possible:
  - R = Ringing (a connection is being established)

	<ul style="list-style-type: none"><li>• C = Connected (at least 2 participants are calling each other)</li><li>• H = Hold (a participant is on hold)</li><li>• Q = Queued (a participant has been queued)</li><li>• W = Wrap-up (wrap-up time)</li></ul>
6	Shows tagging and audio analysis data (e. g. found keywords). The line is only displayed if information is available.
7	Shows the conversation. For further information see <a href="#">chapter "Display of the loading states", p. 61</a> .
8	Shows the end time of the loaded conversation.  If several conversations have been loaded in 1 track, the end time of the last conversation is displayed here.

#### 10.4      **Message Viewer**

The Message Viewer serves to display chat texts or text messages (SMS or SDS).








Fig. 105: Message Viewer

1	Main view	Displayed chat texts or text messages. See <a href="#">chapter "Main view", p. 76</a> .
2	<i>Display status changes</i>	<input checked="" type="checkbox"/> = Displays the status changes. <input type="checkbox"/> = Does not displays the status changes.
3		Minimizes the on-screen display to the program icon in the taskbar.

	(Minimize)	
4		Maximizes the on-screen display to full-screen size.
	(Maximize)	
		Reduces the on-screen display to the most recently selected reduced window size.
	(Reconstruct)	
5		Closes the window of the Message Viewer.
	(Close)	

#### 10.4.1 Main view

The main view displays chat texts or text messages.




Fig. 106: Message Viewer without the display of the status changes (example)




Fig. 107: Message Viewer with the display of the status changes (example)

The chat texts or text messages are displayed sorted by date and time. The most recent message is displayed at the bottom.

On the left of the main view, the basic color of the conversation is displayed. If several conversations have been loaded, the basic colors on the left indicate which chat texts or text messages belong together.

## List of figures

Fig. 1	Login screen.....	9
Fig. 2	Single login.....	9
Fig. 3	Your password has expired.....	10
Fig. 4	Login .....	10
Fig. 5	Combination login .....	11
Fig. 6	Your password has expired.....	11
Fig. 7	Single login.....	12
Fig. 8	Your password has expired.....	12
Fig. 9	Free seating login.....	12
Fig. 10	Login window .....	13
Fig. 11	Request password .....	13
Fig. 12	Welcome screen .....	15
Fig. 13	Navigation bar .....	17
Fig. 14	Change language.....	18
Fig. 15	Installed Product Versions .....	18
Fig. 16	Additional Information .....	19
Fig. 17	Change password .....	19
Fig. 18	Change replay server.....	19
Fig. 19	Player settings.....	20
Fig. 20	Change navigation bar .....	20
Fig. 21	Main view WEBcommand (example) .....	22
Fig. 22	Toolbar WEBcommand .....	23
Fig. 23	Detail view (example).....	24
Fig. 24	Main view .....	26
Fig. 25	Changing pages .....	29
Fig. 26	Toolbar of the main view .....	29
Fig. 27	Load selected conversations.....	31
Fig. 28	Select conversations .....	32
Fig. 29	Save as .....	32
Fig. 30	Save conversations .....	33
Fig. 31	Select conversations .....	34
Fig. 32	Add litigation hold.....	34
Fig. 33	Display of a conversation in litigation hold mode .....	34
Fig. 34	Select conversations .....	34
Fig. 35	Remove litigation hold.....	35
Fig. 36	Adjust table of the main view (example) .....	35
Fig. 37	Search criteria (example).....	37
Fig. 38	Saved search settings (example).....	38
Fig. 39	Search Criteria (example) .....	39
Fig. 40	Save search settings (example).....	40
Fig. 41	Save search settings (example).....	40

Fig. 42	Saved search settings (example).....	41
Fig. 43	Saved search settings loaded (example).....	41
Fig. 44	Saved search settings (example).....	42
Fig. 45	Saved search settings loaded (example).....	42
Fig. 46	Saved search settings (example).....	42
Fig. 47	Saved search settings loaded (example).....	43
Fig. 48	Saved search settings (example).....	43
Fig. 49	Enter search criteria (example).....	44
Fig. 50	Search criterion tagged as favorite (example).....	44
Fig. 51	Search criterion not tagged as favorite (example).....	45
Fig. 52	Detail view (example).....	46
Fig. 53	Tab Details (example).....	47
Fig. 54	Tab Participants (example).....	47
Fig. 55	Tab Additional Data (example).....	48
Fig. 56	Select conversation (example).....	48
Fig. 57	Tab Additional Data (example).....	48
Fig. 58	Main view Recording View (example).....	49
Fig. 59	Changing pages.....	51
Fig. 60	Toolbar Recording View.....	51
Fig. 61	Load selected recording.....	52
Fig. 62	Select recording.....	53
Fig. 63	Save as.....	53
Fig. 64	Save conversations.....	54
Fig. 65	Detail view (example).....	55
Fig. 66	Tab Details (example).....	56
Fig. 67	Tab Participants (example).....	57
Fig. 68	Tab Additional Data (example).....	57
Fig. 69	Select conversation (example).....	57
Fig. 70	Tab Additional Data (example).....	58
Fig. 71	Welcome screen (example).....	59
Fig. 72	Replay bar in the full view.....	59
Fig. 73	Replay bar in compressed view.....	59
Fig. 74	Meta data loaded completely.....	61
Fig. 75	Meta data for the recording is missing.....	61
Fig. 76	Defective packet in the meta data of the recording (full view).....	61
Fig. 77	Missing packet in the meta data of the recording (full view).....	61
Fig. 78	Defective or missing packet in the meta data of the recording (compressed view).....	61
Fig. 79	Data buffer empty/loaded.....	61
Fig. 80	Data buffer not loaded completely.....	62
Fig. 81	Data buffer not loaded completely.....	62
Fig. 82	Packet is muted during the recording.....	62
Fig. 83	Conversation section muted.....	62

Fig. 84	The recording contains data which is not supported.....	62
Fig. 85	Emotions detected in a conversation (example) .....	62
Fig. 86	Save as .....	66
Fig. 87	Save conversations .....	67
Fig. 88	Tagging editor .....	68
Fig. 89	Tagging editor with entered comment (example).....	68
Fig. 90	Conversation with tagged conversation section (example).....	68
Fig. 91	Displayed information details (example) .....	68
Fig. 92	Displayed information details (example) .....	69
Fig. 93	Edit tagging (example) .....	69
Fig. 94	Displayed information details (example) .....	69
Fig. 95	Muting for selected participants (example) .....	70
Fig. 96	Conversation with muted conversation section (example).....	70
Fig. 97	Displayed mute section details (example).....	71
Fig. 98	Mute Section Details (example) .....	71
Fig. 99	Edit mute section (example).....	71
Fig. 100	Mute Section Details (example) .....	72
Fig. 101	Conversation with replay loop .....	72
Fig. 102	Video Viewer (example).....	73
Fig. 103	Option bar .....	74
Fig. 104	Replay bar.....	74
Fig. 105	Message Viewer.....	75
Fig. 106	Message Viewer without the display of the status changes (example).....	76
Fig. 107	Message Viewer with the display of the status changes (example).....	77



## List of tables

Tab. 1	Licenses of ASC.....	8
Tab. 2	Optional licenses of ASC .....	8
Tab. 3	Module descriptions .....	17
Tab. 4	Information .....	18
Tab. 5	Call up online help.....	20
Tab. 6	Main view - change sort sequence.....	45
Tab. 7	Main view - change sort sequence.....	54

## Glossary

### MP3

Description of the digitally saved audio data. MP3 compression works by reducing (or approximating) the accuracy of certain components of sound that are considered (by psychoacoustic analysis) to be beyond the hearing capabilities of most humans. The remaining audio information is then recorded in a space-efficient manner. (Source: Wikipedia 9th July 2020)

### PBX

Private Branch Exchange

### PCM

Pulse Code Modulation is an uncompressed pulse modulation method which transforms a time- and value-continuous analog signal into a time- and value-discrete digital signal. It is used in audio technology, for example in the context of the G.711 standard and in video technology for digital video signals in compliance with the ITU-R BT 601 standard. (Source: Wikipedia 12th June 2018)

### SSL

Secure Socket Layer

### TLS

Transport Layer Security; previously known as Secure Sockets Layer (SSL), is a hybrid encryption protocol for safe data transmission in the Internet. Since version 3.0, the SSL protocol is developed under the new name TLS.

### URL

Uniform resource locator. Identifies and locates a resource (e. g. a website) about the used access method (e. g. the used network protocol as HTTP or FTP) and the location of the resource in the computer network. (Source: Wikipedia 20th November 2013)

### Video data

Video data can either consist of camera recordings of a video call or of screen recordings.

### Video recording

A video recording can either consist of a screen video or of a camera video.

### WAVE

The WAVE file format is a container format to digitally save audio files. It is based on the Resource Interchange File Format (RIFF) which is defined by Microsoft for Windows. A WAVE file already contains information about the format of the audio data before the audio data are actually stored.

### XML

Extensible Markup Language is a human-readable and machine-readable language which defines a set of rules for encoding documents.